Peng3d Documentation

Release 1.12.0

notna

Contents

1	Guid	es	3				
	1.1	Installation	3				
	1.2	Quickstart	4				
	1.3	Designing a basic 3D Application with peng3d	10				
2		peng3d - Peng3D main module					
	2.1	peng3d.peng - Main Engine class	11				
	2.2	peng3d.window - Windowing with batteries included	13				
	2.3	peng3d.layer - Extensible 2D/3D Layering	15				
	2.4	peng3d.menu - Flexible menu system	17				
	2.5	peng3d.gui - 2D Widget based GUI System	18				
	2.6 2.7	peng3d.gui.widgets - 2D GUI Widget Base classes	20 23				
	2.7	peng3d.gui.button-Button Widgets	23 27				
	2.9	peng3d.gui.layout - Layout Helper Classes	31				
	2.10	peng3d.gui.layered - Layered Widgets	33				
	2.10	peng3d.gui.container - GUI Container and Scrolling system	39				
	2.12	peng3d.gui.text-Textual Widgets	41				
	2.13	peng3d.gui.slider - Slider and Progressbar Widgets	43				
	2.14	peng3d.gui.style-Generic Styles for Widgets	46				
	2.15	peng3d.resource - Resource loading system	51				
	2.16	peng3d.i18n - Lightweight Translation Manager	52				
	2.17	peng3d.model - Model and Animation system	54				
	2.18	peng3d.camera - Camera System	60				
	2.19	peng3d.world - World, Terrain and Actor management	61				
	2.20	peng3d.actor - Extendable Actor System	63				
	2.21	peng3d.actor.player-Player Actors	64				
	2.22	peng3d.keybind-Dynamic Keybinding System	66				
	2.23	peng3d.config-Configuration system	68				
	2.24	peng3d.util-Utility Functions and Classes	68				
	2.25	peng3d.util.gui - GUI Utility Functions and Classes	71				
	2.26	peng3d.util.types-Custom Types	71				
	2.27	peng3d.version - Version information	72				
3	Even	ts used by Peng3d	73				
	3.1	Peng3d Events using sendEvent()	73				
	3.2	Pyglet Events using sendPygletEvent()	76				

4	Configuration Options for peng3d						
	4.1	Graphic Settings/OpenGL Base State	77				
	4.2	Controls	78				
	4.3	Debug Options	80				
	4.4	Resource Options	80				
	4.5	Translation Options	81				
	4.6	Event Options	81				
	4.7	Other Options	81				
5	Indices and tables		83				
Python Module Index							
In	ndex						

Contents:

Contents 1

2 Contents

CHAPTER 1

Guides

This part of the documentation contains guides related to various parts of peng3d.

Contents:

1.1 Installation

There are several different ways to install peng3d. The most common ways are listed below.

1.1.1 Using pip

This is by far the simplest way to install peng3d. Simply run the following command:

```
$ pip install peng3d
```

You may also wish to add peng3d to your requirements.txt or similar file.

See also:

See the documentation of the Requirements File Format for more details regarding dependency specification.

1.1.2 From source

If you wish to install a development version that is not available on PyPI, you can also install peng3d directly from its source code.

First, you'll have to download the code somewhere. This can be done in any way you like, but here is how it can be done using git:

```
$ git clone https://github.com/not-na/peng3d.git
$ cd peng3d
```

After having downloaded the source code, you can now install it using the setup.py file:

```
$ python setup.py install
```

If there weren't any errors, peng3d should now be installed.

1.1.3 Where to go next

After having installed peng3d, you may wish to look at the *Quickstart* Guide for a simple and fast introduction to peng3d or the *Designing a basic 3D Application with peng3d* Guide for a more in-depth guide.

There are also some examples available in the examples / folder on the main repository.

1.2 Quickstart

In this guide, we'll learn how to create a simple GUI using peng3d.

See also:

For a more complex example, see Designing a basic 3D Application with peng3d.

1.2.1 Basic Structure

In this guide, we will be writing our app using only a single Python file for simplicity. For more complex projects, it is recommended to split your application by menus or even submenus into different files.

First, here's the minimum example required to show anything with peng3d:

```
import peng3d


peng = peng3d.Peng()

peng.createWindow(caption="Hello World!", resizable=True)

main_menu = peng3d.Menu("main", peng.window)
peng.window.addMenu(main_menu)

peng.window.changeMenu("main")
peng.run()
```

If you run the app now, you should see a black window with a title of Hello World!:



While most of the lines should be fairly self-explanatory, let's go through them one by one.

First, we start by importing peng3d and creating an instance of the peng3d.Peng() class:

```
import peng3d
peng = peng3d.Peng()
```

There should only be one instance of this class per app, shared between all components. It manages the event system and some other globally shared resources.

Next, we create our window with the desired caption:

```
peng.createWindow(caption="Hello World!", resizable=True)
```

Since we want to keep this example very simple, we only pass a caption and activate resizing. All arguments to Peng.createWindow() are optional and should be passed as keyword arguments. Any arguments not recognized by peng3d are passed through to the underlying PengWindow class, which will in turn pass through unrecognized arguments to pyglet.

See also:

See the pyglet.window module docs for a list of all arguments.

Now that we have created our window, we'll create our first menu and register it:

1.2. Quickstart 5

```
main_menu = peng3d.Menu("main", peng.window)
peng.window.addMenu(main_menu)
```

The basic Menu class is designed for layer-based rendering. We will later change this, since we want to create a GUI with widgets.

Also, we always need to register menus, so it is a good practice to always register a menu right after creating it.

Lastly, we'll switch to our main menu and start the application:

```
peng.window.changeMenu("main")
peng.run()
```

The call to changeMenu () can be used to switch between different menus, here we use it to define which menu our app starts with. Note that we pass in the name of our menu, not the menu object itself.

The final call to peng.run() starts the internal event loop of pyglet and blocks until the application exits, usually by clicking the X button.

Note: The code described in this subsection can also be found in examples/quickstart/quickstart_basic.py here.

1.2.2 Creating our first widget

Now that we have a basic skeleton running, let's add some actual functionality. We'll modify the code from the previous subsection bit by bit.

First, lets switch to a more advanced GUIMenu instead of the simple Menu we used earlier.

Note: For most widget-oriented apps, this is what you'll use, although custom 3D canvases usually use a plain Menu with a GUILayer for overlayed widgets.

To do this, we'll first change the class name:

```
main_menu = peng3d.GUIMenu("main", peng.window)
```

Then, let's set the background to a more appealing color. For now, we'll use a light grey, although many more variants are possible. You could even use an image or a custom callback as a background. To set the background, simply call GUIMenu.setBackground() with the color you want:

```
main_menu.setBackground([240, 240, 240])
```

By setting the background in the menu instead of the submenu, all submenus of this menu will automatically inherit the background unless they overwrite it. This makes it easier to e.g. swap themes.

If you try to run the app now, you'll notice that it won't start. This is because GUIMenu menus require an active submenu at all times that they are active. So, let's add a submenu:

```
main_main = peng3d.SubMenu("main_sub", main_menu, peng.window, peng)
```

While it may not matter much in this simple app, we have chosen a name for this submenu that is different from the main menu. Any string can be used as a name, so feel free to create your own naming convention.

6 Chapter 1. Guides

Note: While submenus of different menus could have identical names, this is strongly discouraged, as it can lead to confusion in larger projects. Ideally, each named object should have a unique name.

We'll also have to tell the main menu to use this submenu, just before it is activated itself:

```
main_menu.changeSubMenu("main_sub")
```

If you run the app now, you should see a grey window instead of a black window:

```
Hello World!

— □ &
```

Now, this is a bit better than just a black window, but not by much. Let's go a bit further and add a single button that prints whenever it is clicked.

To do this, we'll have to first create the button and register it:

```
button = peng3d.Button(
   "btn",
   main_main,
   pos=[100, 100],
   size=[200, 100],
   label="Press me!",
   borderstyle="oldshadow",
```

(continues on next page)

1.2. Quickstart 7

(continued from previous page)

```
)
main_main.addWidget(button)
```

The Button class takes a lot of arguments, so let's go over them.

In the first line, we pass the name of the button. Here, the same caveats apply as with submenu and menu names. We also pass the submenu this widget belongs to, from which the window and Peng singleton references are gathered.

In the next two lines, we pass the position and size of the widget.

Note: Positions in peng3d widgets are always from the bottom-left corner of the screen. Both positions and sizes are in pixels.

Next, we pass the label. For now, we give it a static label, though peng3d also supports easy translation capabilities.

Lastly, we pass what style of border to use. There are several border styles available, further information is available in the documentation of the *Button* class.

See also:

There are many more optional arguments that the Button class can take. See the API documentation for details.


Now, we have a button. But it does not do anything yet, so let's add an action that prints something whenever it is called:

```
button.addAction("click", print, "Clicked!")
```

The addAction() method is quite flexible. It takes the name of the action as the first parameter, a function to call as the second parameter and passes all other arguments to each call of the function. So while we could write a one-line function to print out our message, we can just pass the argument to print. Obviously, you'll still have to write proper functions or methods for more complicated handlers.

Now, let's take a look at our current app:

8 Chapter 1. Guides



If you run the app yourself, try clicking on the button and watching the console output. You should see Clicked! every time you release the button.

If you want, try playing around with the parameters to the Button class and see how they effect the look or behaviour of the app.

Once you are done, move on to the next subsection, where we learn how to use and switch between multiple menus.

Note: The code described in this subsection can also be found in examples/quickstart/quickstart_widget.py here.

1.2.3 Switching between menus

Todo: Write this subsection

1.2.4 Dynamically adjusting our layout to the window size

1.2. Quickstart 9

Todo: Write this subsection

1.2.5 Further reading

There are other, more advanced guides available. For example, take a look at *Designing a basic 3D Application with peng3d*.

See also:

See the examples / folder on the main repository for more examples of various peng3d features.

1.3 Designing a basic 3D Application with peng3d

Contents:

1.3.1 Introduction

Todo: Write this section

Todo: Write this guide

Todo: Add a full game tutorial (maybe a simple minecraft clone)

10 Chapter 1. Guides

peng3d - Peng3D main module

This Module represents the root of the peng3d Engine.

Most classes contained in submodules are available under the same name, e.g. you can use peng3d.Peng() instead of peng3d.peng.Peng(). Note that for compatibility reasons, peng3d.window is not available by default and will need to be imported directly.

*- importing submodules should be safe as most modules define an __all__ variable.

2.1 peng3d.peng - Main Engine class

```
class peng3d.peng.Peng(cfg: Optional[peng3d.config.Config] = None, *, style: Optional[Dict[str, Union[float, str, Type[Borderstyle]]]] = None)
```

This Class should only be instantiated once per application, if you want to use multiple windows, see createWindow().

An Instance of this class represents the whole Engine, with all accompanying state and window/world objects.

Be sure to keep your instance accessible, as it will be needed to create most other classes.

```
addEventListener (event: str, func: Callable, raiseErrors: bool = False)
Adds a handler to the given event.
```

A event may have an arbitrary amount of handlers, though assigning too many handlers may slow down event processing.

For the format of event, see sendEvent ().

func is the handler which will be executed with two arguments, event_type and data, as supplied to sendEvent().

If raiseErrors is True, exceptions caused by the handler will be re-raised. Defaults to False.

```
\verb"addPygletListener" (\textit{event\_type: str}, \textit{handler: Callable})
```

Registers an event handler.

The specified callable handler will be called every time an event with the same event_type is encountered.

All event arguments are passed as positional arguments.

This method should be used to listen for pyglet events. For new code, it is recommended to use addEventListener() instead.

See handleEvent () for information about tunneled pyglet events.

For custom events, use addEventListener() instead.

createWindow (cls=window.PengWindow, *args, **kwargs)

Creates a new window using the supplied cls.

If cls is not given, peng3d.window.PengWindow() will be used.

Any other positional or keyword arguments are passed to the class constructor.

Note that this method currently does not support using multiple windows.

Todo: Implement having multiple windows.

delEventListener (event: str, func: Callable)

Removes the given handler from the given event.

If the event does not exist, a NameError is thrown.

If the handler has not been registered previously, also a NameError will be thrown.

handleEvent (event_type: str, args: Tuple, window: Optional[pyglet.window.Window] = None)
Handles a pyglet event.

This method is called by PengWindow.dispatch_event() and handles all events.

See $register {\it Event Handler}$ () for how to listen to these events.

This method should be used to send pyglet events. For new code, it is recommended to use <code>sendEvent()</code> instead. For "tunneling" pyglet events, use event names of the format pyglet:<event> and for the data use {"args":<args as list>, "window":<window object or none>, "src":<event source>, "event_type":<event type>}

Note that you should send pyglet events only via this method, the above event will be sent automatically.

Do not use this method to send custom events, use <code>sendEvent()</code> instead.

registerEventHandler (event_type: str, handler: Callable)

Registers an event handler.

The specified callable handler will be called every time an event with the same event_type is encountered.

All event arguments are passed as positional arguments.

This method should be used to listen for pyglet events. For new code, it is recommended to use addEventListener() instead.

See handleEvent () for information about tunneled pyglet events.

For custom events, use addEventListener() instead.

run (evloop: Optional[pyglet.app.EventLoop] = None)

Runs the application main loop.

This method is blocking and needs to be called from the main thread to avoid OpenGL bugs that can occur.

evloop may optionally be a subclass of pyglet.app.base.EventLoop to replace the default event

```
sendEvent (event: str, data: Optional[dict] = None)
```

Sends an event with attached data.

event should be a string of format <namespace>:<category1>.<subcategory2>.<name>. There may be an arbitrary amount of subcategories. Also note that this format is not strictly enforced, but rather recommended by convention.

data may be any Python Object, but it usually is a dictionary containing relevant parameters. For example, most built-in events use a dictionary containing at least the peng key set to an instance of this class.

If there are no handlers for the event, a corresponding message will be printed to the log file. To prevent spam, the maximum amount of ignored messages can be configured via events.maxiqnore and defaults to 3.

If the config value debug.events.dumpfile is a file path, the event type will be added to an internal list and be saved to the given file during program exit.

sendPygletEvent (event_type: str, args: Tuple, window: Optional[pyglet.window.Window] = None) Handles a pyglet event.

This method is called by PengWindow.dispatch_event() and handles all events.

See registerEventHandler() for how to listen to these events.

This method should be used to send pyglet events. For new code, it is recommended to use <code>sendEvent()</code> For "tunneling" pyglet events, use event names of the format pyglet:<event> and for the data use { "args ":<args as list>, "window":<window object or none>, "src":<event source>, "event_type":<event type>}

Note that you should send pyglet events only via this method, the above event will be sent automatically.

Do not use this method to send custom events, use <code>sendEvent()</code> instead.

class peng3d.peng.HeadlessPeng(cfg: Union[dict, peng3d.config.Config, None] = None) Variant of peng that should work without having pyglet installed.

This class is intended for use in servers as a drop-in replacement for the normal engine class.

Note that this class is a work in progress and should not yet be relied upon.

2.2 peng3d.window - Windowing with batteries included

```
class peng3d.window.PengWindow(peng: peng3d.Peng, *args, **kwargs)
     Main window class for peng3d and subclass of pyglet.window.Window().
     This class should not be instantiated directly, use the Peng.createWindow() method.
     addMenu (menu: peng3d.BasicMenu) → peng3d.BasicMenu
          Adds a menu to the list of menus.
     changeMenu (menu: str) \rightarrow None
```

Changes to the given menu.

menu must be a valid menu name that is currently known.

dispatch_event (event_type: str, *args)

Internal event handling method.

This method extends the behavior inherited from pyglet.window.Window.dispatch_event() by calling the various handleEvent() methods.

By default, Peng.handleEvent(), handleEvent() and Menu.handleEvent() are called in this order to handle events.

Note that some events may not be handled by all handlers during early startup.

menu

Property for accessing the currently active menu.

Always equals self.menus[self.activeMenu].

This property is read-only.

on_draw()

Clears the screen and draws the currently active menu.

run (evloop: Optional[pyglet.app.EventLoop] = None) \rightarrow None

Runs the application in the current thread.

This method should not be called directly, especially when using multiple windows, use Peng.run() instead.

Note that this method is blocking as rendering needs to happen in the main thread. It is thus recommendable to run your game logic in another thread that should be started before calling this method.

evloop may optionally be a subclass of pyglet.app.base.EventLoop to replace the default event loop.

set2d()

Configures OpenGL to draw in 2D.

Note that wireframe mode is always disabled in 2D-Mode, but can be re-enabled by calling glPolygonMode(GL_FRONT_AND_BACK, GL_LINE).

set3d(cam)

Configures OpenGL to draw in 3D.

This method also applies the correct rotation and translation as set in the supplied camera cam. It is discouraged to use glTranslatef() or glRotatef() directly as this may cause visual glitches.

If you need to configure any of the standard parameters, see the docs about $Configuration \ Options \ for \ peng3d.$

The graphics.wireframe config value can be used to enable a wireframe mode, useful for debugging visual glitches.

set fps(fps: Optional[float])

Sets the new FPS limit.

This limit will be used until the application closes or this method is called again.

A value of None will cause the FPS limit to be disabled.

Note that this is only a limit, which may or may not be fulfilled depending on available resources.

Note: By default, pyglet only redraws the window when an event arrives. To force a certain redraw rate (which still respects system performance), call pyglet.clock.schedule_interval() once during initialization with a dummy function and your desired refresh rate in seconds.

Parameters fps -

Returns

setup()

Sets up the OpenGL state.

This method should be called once after the config has been created and before the main loop is started. You should not need to manually call this method, as it is automatically called by run().

Repeatedly calling this method has no effects.

setupFog()

Sets the fog system up.

The specific options available are documented under graphics.fogSettings.

setupLight()

Sets the light system up.

The specific options available are documented under graphics.lightSettings.

Note that this feature is currently not implemented.

toggle_exclusivity(override=None)

Toggles mouse exclusivity via pyglet's set_exclusive_mouse() method.

If override is given, it will be used instead.

You may also read the current exclusivity state via exclusive.

2.3 peng3d.layer - Extensible 2D/3D Layering

Base layer class.

A Layer can be used to separate background from foreground or the 3d world from a 2d HUD.

This class by itself does nothing, you will need to subclass it and override the draw() method.

$\mathtt{draw}() \rightarrow \mathsf{None}$

Called when this layer needs to be drawn.

Override this method in subclasses to redefine behavior.

on_menu_enter(old)

Custom fake event handler called by Menu.on_enter() for every layer.

Useful for adding and removing event handlers per layer.

on_menu_exit (new)

Custom fake event handler called by Menu.on_exit() for every layer.

Useful for adding and removing event handlers per layer.

$\verb"on_redraw"() \to None"$

Called whenever the Layer should redraw itself.

Note that this method should not be called manually, instead call redraw().

Returns None

```
postdraw() \rightarrow None
```

Called after the draw() method is called.

This method can be used to reset OpenGL state to avoid conflicts with other code.

Override this method in subclasses to redefine behavior.

$predraw() \rightarrow None$

Called before the *draw()* method is called.

This method is used in the Layer2D() and Layer3D() subclasses for setting OpenGL state.

Override this method in subclasses to redefine behavior.

```
redraw() \rightarrow None
```

Call this to redraw the layer.

Note that the redraw will not happen immediately, rather on the next frame that this layer is rendered. This massively improves performance.

Returns

```
class peng3d.layer.Layer2D (menu: peng3d.menu.BasicMenu, window: Any = None, peng: Any = None)
```

2D Variant of Layer () and a subclass of the former.

This class makes use of the <code>predraw()</code> method to configure OpenGL to draw 2-Dimensionally. This class uses <code>PengWindow.set2d()</code> to set the 2D mode.

When overriding the predraw () method, make sure to call the superclass.

predraw()

Uses PengWindow.set2d() to enable a 2D OpenGL state.

```
class peng3d.layer.Layer3D (menu: peng3d.menu.BasicMenu, window: Any = None, peng: Any = None, cam: peng3d.camera.Camera = None)
```

3D Variant of Layer () and a subclass of the former.

This class works the same as Layer2D(), only for 3D drawing instead. This class uses PengWindow. set3d() to set the 3D mode.

Also, the correct glTranslatef() and glRotatef() are applied to simplify drawing objects. When writing the draw() method of this class, you will only need to use world coordinates, not camera coordinates. This allows for easy building of Games using First-Person-Perspectives.

predraw()

Uses PengWindow.set3d() to enable a 3D OpenGL state.

Layer variant wrapping the supplied pyglet group.

group may only be an instance of pyglet.graphics.Group, else a TypeError will be raised.

Also note that both the predraw () and postdraw () methods are overwritten by this class.

See also:

For more information about pyglet groups, see the pyglet docs.

postdraw()

Re-sets the previous state.

predraw()

Sets the group state.

```
class peng3d.layer.LayerWorld(menu: peng3d.menu.BasicMenu, window: Any = None, peng: Any = None, world=None, viewname: str = None)

Subclass of Layer3D() implementing a 3D Layer showing a specific WorldView.
```

All arguments passed to the constructor should be self-explanatory.

Note that you may not set any of the attributes directly, or crashes and bugs may appear indirectly within a certain during future re-drawing of the screen.

draw()

Draws the view using the World.render3d() method.

on_menu_enter(old)

Passes the event through to the WorldView to allow for custom behavior.

on_menu_exit (new)

Same as on_menu_enter().

predraw()

Sets up the attributes used by Layer3D() and calls Layer3D.predraw().

setView (*name: str*) \rightarrow None

Sets the view used to the specified name.

The name must be known to the world or else a ValueError is raised.

2.4 peng3d.menu - Flexible menu system

Menu base class without layer support.

Each menu is separated from the other menus and can be switched between at any time.

Actions supported by default:

enter is triggered everytime the on_enter() method has been called.

exit is triggered everytime the on_exit () method has been called.

See also:

See Menu () for more information.

addWorld(world)

Adds the given world to the internal list.

Worlds that are registered via this method will get all events that are given to this menu passed through.

This mechanic is mainly used to implement actor controllers.

draw()

This method is called if it is time to render the menu.

Override this method in subclasses to customize behavior and actually draw stuff.

on_enter(old)

This fake event handler will be called every time this menu is entered via the PengWindow. changeMenu() method.

This handler will not be called if this menu is already active.

```
on exit (new)
```

This fake event handler will be called every time this menu is exited via the PengWindow. changeMenu() method.

This handler will not be called if this menu is the same as the new menu.

```
class peng3d.menu.Menu (name: str, window: peng3d.window.PengWindow, peng: Any = None) Subclass of BasicMenu adding support for the Layer class.
```

This subclass overrides the draw and init method, so be sure to call them if you override them.

```
addLayer (layer: peng3d.layer.Layer, z: int = -1) \rightarrow None
```

Adds a new layer to the stack, optionally at the specified z-value.

layer must be an instance of Layer or subclasses.

z can be used to override the index of the layer in the stack. Defaults to -1 for appending.

$\mathtt{draw}() \rightarrow \mathrm{None}$

Draws the layers in the appropriate order.

Layers that have their enabled attribute set to False are skipped.

```
on enter (old)
```

```
Same as <code>BasicMenu.on_enter()</code>, but also calls <code>Layer.on_menu_enter()</code> on every layer.
```

on exit (new)

Same as BasicMenu.on_exit(), but also calls Layer.on_menu_exit() on every layer.

2.5 peng3d.gui - 2D Widget based GUI System

Note that widgets are not managed directly by this class, but rather by each SubMenu.

```
addSubMenu (submenu: peng3d.gui.SubMenu) \rightarrow None Adds a SubMenu to this Menu.
```

Note that nothing will be displayed unless a submenu is activated.

Deprecated since version 1.12.0: This method is no longer needed in most cases, since submenus now register themselves.

```
changeSubMenu (submenu: str) \rightarrow None
```

Changes the submenu that is displayed.

Raises ValueError – if the name was not previously registered

```
\mathtt{draw}() \rightarrow \mathrm{None}
```

Draws each menu layer and the active submenu.

Note that the layers are drawn first and may be overridden by the submenu and widgets.

```
on_enter(old)
```

Same as BasicMenu.on_enter(), but also calls Layer.on_menu_enter() on every layer.

submenu

Property containing the SubMenu instance that is currently active.

Sub Menu of the GUI system.

Changed in version 1.12: Sub menus are automatically registered with their parent, using addSubMenu() is no longer necessary.

Actions supported by default:

enter is triggered everytime the on_enter() method has been called.

exit is triggered everytime the on_exit() method has been called.

send_form is triggered if the contained form is sent by either pressing enter or calling send_form().

addWidget (widget: peng3d.gui.widgets.BasicWidget, order_key: int = 0) \rightarrow None Adds a widget to this submenu.

order_key optionally specifies the "layer" this widget will be on. Note that this does not work with batched widgets. All batched widgets will be drawn before widgets that use a custom draw() method.

Deprecated since version 1.12.0: This method is no longer needed in most cases, since widgets now register themselves by default.

$delWidget (widget: str) \rightarrow None$

Deletes the widget by the given name.

Note that this feature is currently experimental as there seems to be a memory leak with this method.

$\mathtt{draw}\,() \to \mathrm{None}$

Draws the submenu and its background.

Note that this leaves the OpenGL state set to 2d drawing.

```
form\_valid(ctx=None) \rightarrow bool
```

Called to pre-check if a form is valid.

Should be overridden by subclasses.

By default, this always returns true.

Parameters ctx - Arbitrary context

Returns If the form is valid

getWidget (name: str) → peng3d.gui.widgets.BasicWidget

Returns the widget with the given name.

$send_form(ctx=None) \rightarrow bool$

Triggers whatever form data is entered to be sent.

Only causes action send_form to be sent if submenu is active and form_valid() returns true.

The given context is stored in form_ctx.

Parameters ctx – Arbitrary context

Returns If the form was actually sent

```
setBackground (bg: Union[Layer, Callable, list, tuple, Background, str, Type[DEFER_BG]]) \rightarrow
     None Sets the background of the submenu.
```

The background may be a RGB or RGBA color to fill the background with.

Alternatively, a peng3d.layer.Layer instance or other object with a .draw() method may be supplied. It is also possible to supply any other method or function that will get called.

Also, the strings flat, gradient, oldshadow and material may be given, resulting in a background that looks similar to buttons.

If the Background is None, the default background of the parent menu will be used.

Lastly, the string "blank" may be passed to skip background drawing.

```
class peng3d.gui.GUILayer(name:
                                                       peng3d.menu.Menu,
                                                                                      Op-
                                        str,
                                              тепи:
                                                                          window:
                               tional[peng3d.window.PengWindow] = None,
                                                                           peng:
                                                                                      Op-
                               tional[peng3d.Peng] = None
    Hybrid of GUIMenu and peng3d.layer.Layer2D.
```

This class allows you to create Head-Up Displays and other overlays easily.

```
\mathtt{draw}() \rightarrow \mathrm{None}
         Draws the Menu.
```

2.6 peng3d.qui.widgets - 2D GUI Widget Base classes

```
class peng3d.gui.widgets.BasicWidget(name:
                                                         Optional[str], submenu:
                                                                                  SubMenu, win-
                                                        Any = None, peng:
                                                                               Any = None, *,
                                                pos: Union[List[float], Callable[[float, float, float,
                                                float], Tuple[float, float]], layout.LayoutCell], size:
                                                Union[List[float], Callable[[float, float], Tuple[float,
                                                float]], None] = None, order_key: Optional[int]
                                                = 0, style:
                                                               Optional[Dict[str, Union[float, str,
                                                Type[Borderstyle]]] = None)
```

Basic Widget class.

pos may be either a list or 2-tuple of (x,y) for static positions or a function with the signature window_width, window_height, widget_width, widget_height returning a tuple.

size is similar to pos but will only get window_width, window_height as its arguments.

Commonly, the lambda lambda sw, sh, bw, bh: (sw/2.-bw/2., sh/2.-bh/2.) is used to center the widget.

Additionally, an instance of a subclass of Layout Cell may be passed as pos. Note that this will automatically override size as well, unless size is also supplied.

The actions available may differ from widget to widget, by default these are used:

- press is called upon starting to click on the widget
- click is called if the mouse is released on the widget while also having been pressed on it before, recommended for typical button callbacks
- context is called upon right-clicking on the widget and may be used to display a context menu
- hover_start signals that the cursor is now hovering over the widget
- hover is called every time the cursor moves while still being over the widget

- hover_end is called after the cursor leaves the widget
- statechanged is called every time the visual state of the widget should change

Deprecated since version 1.12: The window and peng parameters are deprecated and will be removed in peng3d 2.0. They are no longer needed and should be removed from existing code.

Changed in version 1.12: It is no longer necessary to register widgets using addWidget(), widget registration is now automatically performed by widgets themselves.

IS CLICKABLE = False

Class attribute used to signal if widgets of this class are usually clickable.

This attribute is used to fill the initial value of <code>enabled</code> and can therefore be overridden on a widget-by-widget basis.

Note that leaving this set to False will prevent most mouse-related actions from being triggered. This is due to internal optimization and the main benefit of leaving this option off.

clickable

Property used for determining if the widget should be clickable by the user.

This is only true if the submenu of this widget is active and this widget is enabled.

The widget may be either disabled by setting this property or the enabled attribute.

delete()

Deletes resources of this widget that require manual cleanup.

Currently removes all actions, event handlers and the background.

The background itself should automatically remove all vertex lists to avoid visual artifacts.

Note that this method is currently experimental, as it seems to have a memory leak.

$\mathtt{draw}() \rightarrow \mathrm{None}$

Draws all vertex lists associated with this widget.

enabled

Property used for storing whether or not this widget is enabled.

May influence rendering and behavior.

Note that the widget will be immediately redrawn if this property is changed.

$getState() \rightarrow str$

Returns the current state of the widget.

One of "pressed", "hover", "disabled" or "idle". Note that some information may be lost by getting this state, for example it is not possible to know if the widget is hovered or not if "pressed" is returned. However, this should not be a problem for most intended uses of this method.

$on_redraw() \rightarrow None$

Callback to be overridden by subclasses called if redrawing the widget seems necessary.

Note that this method should not be called manually, see redraw() instead.

pos

Property that will always be a 2-tuple representing the position of the widget.

Note that this method may call the method given as pos in the initializer.

The returned object will actually be an instance of a helper class to allow for setting only the x/y coordinate.

This property also respects any Container set as its parent, any offset will be added automatically.

Note that setting this property will override any callable set permanently.

$redraw() \rightarrow None$

Triggers a redraw of the widget.

Note that the redraw may not be executed instantly, but rather batched together on the next frame. If an instant and synchronous redraw is needed, use on_redraw() instead.

registerEventHandlers()

Registers event handlers used by this widget, e.g. mouse click/motion and window resize.

This will allow the widget to redraw itself upon resizing of the window in case the position needs to be adjusted.

size

Similar to pos but for the size instead.

visible

Property used for storing whether or not this widget is enabled.

May influence rendering and behavior.

Note that the widget will be immediately redrawn if this property is changed.

class peng3d.gui.widgets.Background(widget: peng3d.gui.widgets.BasicWidget)

Class representing the background of a widget.

Note that if a background is used as the background of a SubMenu, the SubMenu instance itself should be passed as the widget.

This base class does not do anything.

init bg() \rightarrow None

Called just before the background will be drawn the first time.

Commonly used to initialize vertex lists.

It is recommended to add all vertex lists to the submenu.batch2d Batch to speed up rendering and preventing glitches with grouping.

is_hovering

Read-only helper property for easier access.

Equivalent to widget . is_hovering.

peng

Property for accessing the parent widget's instance of peng3d.peng.Peng.

pressed

Read-only helper property for easier access.

Equivalent to widget.pressed.

redraw_bg() \rightarrow None

Method called by the parent widget every time its Widget.redraw() method is called.

$reg_vlist(vlist: pyglet.graphics.vertexdomain.VertexList) \rightarrow None$

Registers a vertex list to the internal list.

This allows the class to clean itself up properly during deletion, as the background would still be visible after deletion otherwise.

submenu

Property for accessing the parent widget's submenu.

window

Property for accessing the parent widget's window.

peng3d.gui.widgets.DEFER_BG = <peng3d.gui.widgets._DeferBackgroundSentinel object>
 Sentinel object that may be passed instead of an actual background to signify that the background will be set
later

Differs from passing None, since None will cause an *EmptyBackground* to be unnecessarily created, while *DEFER_BG* simply does nothing.

Note that if the actual background is not set before the first render, a TypeError will be raised.

Subclass of BasicWidget adding support for changing the Background.

If no background is given, an *EmptyBackground* will be used instead.

on_redraw()

Draws the background and the widget itself.

Subclasses should use super () to call this method, or rendering may glitch out.

setBackground (bg: peng3d.gui.widgets.Background) \rightarrow peng3d.gui.widgets.Background Sets the background of the widget.

This may cause the background to be initialized.

class peng3d.gui.widgets.**EmptyBackground**(widget: peng3d.gui.widgets.BasicWidget)
Background that draws simply nothing.

Can be used as a placeholder.

2.7 peng3d.gui.button - Button Widgets

Button Widget allowing the user to trigger specific actions.

By default, this Widget uses ButtonBackground as its Background class.

The border given is in pixels from the left/right and top/bottom, respectively.

The borderstyle may be either flat, which has no border at all, gradient, which fades from the inner color to the background color, oldshadow, which uses a simple fake shadow with the light from the top-left corner and material, which imitates Google Material Design shadows.

Also, the label of the button may only be a single line of text, anything else may produce undocumented behavior.

If necessary, the font size of the Label may be changed via the global Constant LABEL_FONT_SIZE, changes will only apply to Buttons created after change. The text color used is [62,67,73,255] in RGBA and the font used is Arial, which should be available on most systems.

delete()

Deletes resources of this widget that require manual cleanup.

Currently removes all actions, event handlers and the background.

The background itself should automatically remove all vertex lists to avoid visual artifacts.

Note that this method is currently experimental, as it seems to have a memory leak.

label

Property for accessing the label of this Button.

on_redraw()

Draws the background and the widget itself.

Subclasses should use super () to call this method, or rendering may glitch out.

redraw label()

Re-draws the label by calculating its position.

Currently, the label will always be centered on the Button.

Background for the Button Widget.

This background renders the button and its border, but not the label.

getColors()

Overrideable function that generates the colors to be used by various borderstyles.

Should return a 5-tuple of (bg, o, i, s, h).

bg is the base color of the background.

- o is the outer color, it is usually the same as the background color.
- i is the inner color, it is usually lighter than the background color.
- s is the shadow color, it is usually quite a bit darker than the background.
- h is the highlight color, it is usually quite a bit lighter than the background.

getPosSize()

Helper function converting the actual widget position and size into a usable and offsetted form.

This function should return a 6-tuple of (sx, sy, x, y, bx, by) where sx and sy are the size, x and y the position and bx and by are the border size.

All values should be in pixels and already include all offsets, as they are used directly for generation of vertex data.

This method can also be overridden to limit the background to a specific part of its widget.

init_bg()

Called just before the background will be drawn the first time.

Commonly used to initialize vertex lists.

It is recommended to add all vertex lists to the submenu.batch2d Batch to speed up rendering and preventing glitches with grouping.

is_hovering

Read-only helper property to be used by borderstyles for determining if the widget should be rendered as hovered or not.

Note that this property may not represent the actual hovering state, it will always be False if change_on_press is disabled.

pressed

Read-only helper property to be used by borderstyles for determining if the widget should be rendered as pressed or not.

Note that this property may not represent the actual pressed state, it will always be False if change_on_press is disabled.

redraw_bg()

Method called by the parent widget every time its Widget.redraw() method is called.

Subclass of Button using an image as a background instead.

By default, this Widget uses ImageBackground as its Background class.

There are no changes to any other mechanics of the Button, only visually.

Background for the ImageButton Widget.

This background renders a image given based on whether the widget is pressed, hovered over or disabled.

It should also be possible to use this class as a background for most other Widgets.

init bq()

Called just before the background will be drawn the first time.

Commonly used to initialize vertex lists.

It is recommended to add all vertex lists to the submenu.batch2d Batch to speed up rendering and preventing glitches with grouping.

pressed

Read-only helper property to be used by borderstyles for determining if the widget should be rendered as pressed or not.

Note that this property may not represent the actual pressed state, it will always be False if change_on_press is disabled.

redraw_bg()

Method called by the parent widget every time its Widget.redraw() method is called.

class peng3d.gui.button.FramedImageButton (name: Optional[str], submenu: SubMenu, window: Any = None, peng: Any = None, *, pos:

dow: Any = None, peng: Any = None, *, pos: Union[List[float], Callable[[float, float, float]], layout.LayoutCell], size: Union[List[float]], None] = None, float], Tuple[float, float]], None] = None, bg=None, label='Button', font_size=None, font=None, font_color=None, bg_idle=None, bg_hover=None, frame=[[2, 10, 2], [2, 10, 2]], scale=(1, 1), repeat_edge=False, repeat_center=False, tex_size=None, label layer=1)

Subclass of ImageButton adding smart scaling to the background.

By default, this Widget uses FramedImageBackground as its Background class.

frame defines the ratio between the borders and the center. The sum of each item must be greater than zero, else a ZeroDivisionError may be thrown. Note that up to two items of each frame may be left as 0. This will cause the appropriate border or center to not be rendered at all.

tex_size may be left empty if a resource name is passed. It will then be automatically determined.

Todo: Document scale

Background for the FramedImageButton Widget.

This background is similar to ImageBackground, but it attempts to scale smarter with less artifacts.

init_bg()

Called just before the background will be drawn the first time.

Commonly used to initialize vertex lists.

It is recommended to add all vertex lists to the submenu.batch2d Batch to speed up rendering and preventing glitches with grouping.

redraw_bg()

Method called by the parent widget every time its Widget.redraw() method is called.

float], Tuple[float, float]], layout.LayoutCell], size: Union[List[float], Callable[[float, float], *Tuple[float,* float]], None = None,peng3d.gui.widgets.Background = None, border: Optional[Tuple[float, float]] = None, borderstyle: *Union*[Type[Borderstyle], str, None] = None, label: Union[str, LazyTranslator] = 'Button',min_size=None, font_size: Optional[float] = None, *font=None, font_color=None, label_layer=1*)

Variant of Button that stays pressed until clicked again.

This widgets adds the following actions:

- press_down is called upon depressing the button
- press_up is called upon releasing the button
- click is changed to be called on every click on the button, e.g. like press_down and press_up combined

Variant of ToggleButton using a different visual indicator.

By default, this Widget uses CheckboxBackground as its Background class.

Note that the position and size given are for the indicator, the label will be bigger than the given size.

The label given will be displayed to the right of the Checkbox.

```
redraw_label()
```

Re-calculates the position of the Label.

Background for the Checkbox Widget.

This background looks like a button, but adds a square in the middle if it is pressed.

The color of the square defaults to a tone of orange commonly found in GTK GUIs on Ubuntu.

```
init_bg()
```

Called just before the background will be drawn the first time.

Commonly used to initialize vertex lists.

It is recommended to add all vertex lists to the submenu.batch2d Batch to speed up rendering and preventing glitches with grouping.

```
redraw_bg()
```

Method called by the parent widget every time its Widget .redraw() method is called.

2.8 peng3d.gui.menus - Menus and Dialogs

Menus are special submenus that act like modal dialogs.

They include glue code that automatically switches back to the previous submenu after they are left. Note that this will cuase the SubMenu.on_enter() method to be called again.

Since these menus are internally implemented as submenus, they are specific to their Menu, which must be active to be able to use the dialog.

2.8.1 Customization

Menus are customizable via several different means.

If you just want to change the appearance or label of a part of the menu, you can use keyword arguments while initializing the class. For example, setting the label_main argument to the string Hello World! the main label or title of the dialog will now display Hello World! instead of its default value. What exact arguments are supported differs from dialog to dialog.

Note that sometimes specific labels are supported, but not used by default. Just setting these to anything may cause GUI components to be rendered that should not be there.

It is also possible for most of these values to be set on-the-fly via properties on the object they belong to.

For example, the <code>DialogSubMenu.label_main</code> property may be set to change the main label even while the dialog is active.

Note that the values accessible via keyword arguments and properties may differ. This depends on the dialog implementing them.

For clarity, these keyword arguments will from now on be called "labels". This also includes labels that are not strictly text, like the maximum value of a progressbar.

Base Dialog Class.

This class acts as a base class for all other dialog submenus.

When the dialog is entered, the prev_submenu attribute will be set to the name of the previous submenu. This attribute is later used when exiting the dialog.

Dialog submenus also support the basic actions used by all submenus, e.g. enter and exit. Additionally, many dialogs also add actions for whenever a label is changed or the dialog is exited through a special means, e.g. pressing a specific button of multiple presented.

If used by itself, it will display a text centered on the screen with a button below it. Clicking the button will cause the dialog to exit and also the additional click_ok action to be fired.

The labels supported by default are label_main, which defaults to Default Text and is recommended to always be customized, and label_ok, which defaults to OK and may be left as-is.

Subclasses may override these defaults by setting the keys of the same name in the DEFAULT_LABELS class attribute. Note that any unchanged labels must also be declared when overwriting any labels, or they may not be displayed.

Widgets and their initializers are stored in the WIDGETS class attribute, see add_widgets() for more information.

activate()

Helper method to enter the dialog.

Calling this method will simply cause the dialog to become the active submenu.

Note that is not necessary to call this method over changeSubMenu(), as the storing of the previous submenu is done elsewhere.

add btn ok(label ok)

Adds an OK button to allow the user to exit the dialog.

This widget can be triggered by setting the label label_ok to a string.

This widget will be mostly centered on the screen, but below the main label by the double of its height.

add_label_main(label_main)

Adds the main label of the dialog.

This widget can be triggered by setting the label label main to a string.

This widget will be centered on the screen.

add widgets(**kwargs)

Called by the initializer to add all widgets.

Widgets are discovered by searching through the WIDGETS class attribute. If a key in WIDGETS is also found in the keyword arguments and not none, the function with the name given in the value of the key will be called with its only argument being the value of the keyword argument.

For more complex usage scenarios, it is also possible to override this method in a subclass, but the original method should always be called to ensure compatibility with classes relying on this feature.

exitDialog()

Helper method that exits the dialog.

This method will cause the previously active submenu to activate.

label main

Property that proxies the label_main label.

Setting this property will cause the label_main_change action to trigger.

Note that trying to access this property if the widget is not used may cause an error.

label ok

Property that proxies the label_ok label.

Setting this property will cause the label_ok_change action to trigger.

Note that trying to access this property if the widget is not used may cause an error.

Dialog that allows the user to confirm or cancel an action.

By default, the OK button will be hidden and the label_main will be set to Are you sure?.

Clicking the confirm button will cause the confirm action to trigger, while the cancel button will cause the cancel action to trigger.

add_btn_cancel (label_cancel)

Adds a cancel button to let the user cancel whatever choice they were given.

This widget can be triggered by setting the label label_cancel to a string.

This widget will be positioned slightly below the main label and to the right of the confirm button.

add btn confirm(label confirm)

Adds a confirm button to let the user confirm whatever action they were presented with.

This widget can be triggered by setting the label label_confirm to a string.

This widget will be positioned slightly below the main label and to the left of the cancel button.

label_cancel

Property that proxies the label_cancel label.

Setting this property will cause the label_cancel_change action to trigger.

Note that trying to access this property if the widget is not used may cause an error.

label_confirm

Property that proxies the label_confirm label.

Setting this property will cause the label_confirm_change action to trigger.

Note that trying to access this property if the widget is not used may cause an error.

class peng3d.gui.menus.TextSubMenu (name, menu, window, peng, timeout=10, **kwargs)

Dialog without user interaction that can automatically exit after a certain amount of time.

This dialog accepts the timeout keyword argument, which may be set to any time in seconds to delay before exiting the dialog. A value of -1 will cause the dialog to never exit on its own.

Note that the user will not be able to exit this dialog and may believe the program is hanging if not assured otherwise. It is thus recommended to use the *ProgressSubMenu* dialog instead, especially for long-running operations.

Dialog without user interaction displaying a progressbar.

By default, the progressbar will range from 0-100, effectively a percentage.

The auto_exit attribute may be set to control whether or not the dialog will exit automatically when the maximum value is reached.

add_progressbar (label_progressbar)

Adds a progressbar and label displaying the progress within a certain task.

This widget can be triggered by setting the label label progressbar to a string.

The progressbar will be displayed centered and below the main label. The progress label will be displayed within the progressbar.

The label of the progressbar may be a string containing formatting codes which will be resolved via the format () method.

Currently, there are six keys available:

n and value are the current progress rounded to 4 decimal places.

nmin is the minimum progress value rounded to 4 decimal places.

nmax is the maximum progress value rounded to 4 decimal places.

p and percent are the percentage value that the progressbar is completed rounded to 4 decimal places.

By default, the progressbar label will be {percent} % displaying the percentage the progressbar is complete.

auto exit = False

Controls whether or not the dialog will exit automatically after the maximum value has been reached.

label_progressbar

Property that proxies the label_progressbar label.

Setting this property will cause the progressbar label to be recalculated.

Note that setting this property if the widget has not been initialized may cause various errors to occur.

progress_n

Property that proxies the progress_n label.

Setting this property will cause the progressbar label to be recalculated.

Additionally, if the supplied value is higher than the maximum value and auto_exit is true, the dialog will exit.

progress_nmax

Property that proxies the progress_nmax label.

Setting this property will cause the progressbar label to be recalculated.

Note that setting this property if the widget has not been initialized may cause various errors to occur.

progress_nmin

Property that proxies the progress_nmin label.

Setting this property will cause the progressbar label to be recalculated.

Note that setting this property if the widget has not been initialized may cause various errors to occur.

update_progressbar()

Updates the progressbar by re-calculating the label.

It is not required to manually call this method since setting any of the properties of this class will automatically trigger a re-calculation.

```
addCategory (*args, **kwargs)
Proxy for addCategory().
```

add_progressbar (label_progressbar)

Adds a progressbar and label displaying the progress within a certain task.

This widget can be triggered by setting the label label_progressbar to a string.

The progressbar will be displayed centered and below the main label. The progress label will be displayed within the progressbar.

The label of the progressbar may be a string containing formatting codes which will be resolved via the format () method.

Currently, there are six keys available:

n and value are the current progress rounded to 4 decimal places.

nmin is the minimum progress value rounded to 4 decimal places.

nmax is the maximum progress value rounded to 4 decimal places.

p and percent are the percentage value that the progressbar is completed rounded to 4 decimal places.

By default, the progressbar label will be {percent} % displaying the percentage the progressbar is complete.

```
deleteCategory (*args, **kwargs)
    Proxy for deleteCategory ().
updateCategory (*args, **kwargs)
    Proxy for updateCategory ().
```

2.9 peng3d.gui.layout - Layout Helper Classes

```
class peng3d.gui.layout.Layout (peng, parent)
    Base Layout class.
```

This class does not serve any purpose directly other than to be a common base class for all layouts.

Note that layouts can be nested, e.g. usually the first layouts parent is a SubMenu and sub-layouts get a Layout-Cell of their parent layout as their parent.

```
class peng3d.gui.layout.GridLayout (peng, parent, res, border)
    Grid-based layout helper class.
```

This class provides a grid-like layout to its sub-widgets. A border between widgets can be defined. Additionally, all widgets using this layout should automatically scale with screen size.

cell_size

Helper property defining the current size of cells in both x and y axis.

Returns 2-tuple of float

```
get_cell (pos, size, anchor_x='left', anchor_y='bottom', border=1)
```

Returns a grid cell suitable for use as the pos parameter of any widget.

The size parameter of the widget will automatically be overwritten.

Parameters

- pos Grid position, in cell
- size Size, in cells
- anchor_x either left, center or right
- anchor_y either bottom, center or top

Returns LayoutCell subclass

```
class peng3d.gui.layout.LayoutCell
```

Base Layout Cell.

Not to be used directly. Usually subclasses of this class are returned by layouts.

Instances can be passed to Widgets as the pos argument. The size argument will be automatically overridden.

Note that manually setting size will override the size set by the layout cell, though the position will be kept.

pos

Property accessing the position of the cell.

This usually refers to the bottom-left corner, but may change depending on arguments passed during creation

Note that results can be floats.

```
Returns 2-tuple of (x, y)
```

size

Property accessing the size of the cell.

Note that results can be floats.

Returns 2-tuple of (width, height)

2.10 peng3d.gui.layered - Layered Widgets

Layered Widget allowing for easy creation of custom widgets.

A Layered Widget consists of (nearly) any amount of layers in a specific order.

All Layers should be subclasses of BasicWidgetLayer or WidgetLayer.

layers must be a list of 2-tuples of (layer, z index).

```
addLayer (layer, z_index=None)
```

Adds the given layer at the given Z Index.

If z index is not given, the Z Index specified by the layer will be used.

delete()

Deletes all layers within this LayeredWidget before deleting itself.

Recommended to call if you are removing the widget, but not yet exiting the interpreter.

draw()

Draws all layers of this LayeredWidget.

This should normally be unneccessary, since it is recommended that layers use Vertex Lists instead of OpenGL Immediate Mode.

getLayer (name)

Returns the layer corresponding to the given name.

Raises KeyError – If there is no Layer with the given name.

on_redraw()

Draws the background and the widget itself.

Subclasses should use super () to call this method, or rendering may glitch out.

redraw layer(name)

Redraws the given layer.

Raises ValueError – If there is no Layer with the given name.

```
class peng3d.gui.layered.BasicWidgetLayer(name, widget, z_index=None)
```

Base class for all Layers to be used with LayeredWidget ().

Not to be confused with peng3d.layer.Layer(), these classes are not compatible.

It is recommended to use WidgetLayer() instead, since functionality is limited in this basic class.

Note that the z_index will default to a reasonable value for most subclasses and thus is not required to be given explicitly. The z_index for this Layer defaults to 0.

delete()

Deletes this Layer.

Currently only deletes VertexLists registered with regVList().

draw()

Called to draw the layer.

Note that using this function is discouraged, use Pyglet Vertex Lists instead.

If you want to call this method manually, call _draw() instead. This will make sure that predraw() and postdraw() are called.

on_redraw()

Called by the parent widget if this Layer should be redrawn.

Note that it is recommended to call the Baseclass Variant of this Method first when overwriting it. See <code>WidgetLayer.on_redraw()</code> for more information.

postdraw()

Called after calling the draw() Method.

Useful for unsetting OpenGL state.

predraw()

Called before calling the draw() Method.

Useful for setting up OpenGL state.

regVList(vlist)

Registers a vertex list for proper deletion once this Layer gets destroyed.

This prevents visual artifacts from forming during deletion of a layer.

```
class peng3d.gui.layered.WidgetLayer(name, widget, z_index=None, border=[0, 0], offset=[0,
```

Subclass of WidgetLayer() adding commonly used utility features.

This subclass adds a border and offset system.

The border is a 2-tuple of (x_border, y_border). The border is applied to all sides, resulting in the size being decreased by two pixel per pixel border width.

offset is relative to the bottom left corner of the screen.

border

Property to be used for setting and getting the border of the layer.

Note that setting this property causes an immediate redraw.

getPos()

Returns the absolute position and size of the layer.

This method is intended for use in vertex position calculation, as the border and offset have already been applied.

The returned value is a 4-tuple of (sx, sy, ex, ey). The two values starting with an s are the "start" position, or the lower-left corner. The second pair of values signify the "end" position, or upper-right corner.

getSize()

Returns the size of the layer, with the border size already subtracted.

initialize()

Called just before on redraw() is called the first time.

offset

Property to be used for setting and getting the offset of the layer.

Note that setting this property causes an immediate redraw.

```
on redraw()
          Called when the Layer should be redrawn.
          If a subclass uses the initialize () Method, it is very important to also call the Super Class Method
          to prevent crashes.
class peng3d.qui.layered.GroupWidgetLayer(name, widget, group=None, z index=None, bor-
                                                        der=[0, 0], offset=[0, 0]
     Subclass of WidgetLayer () allowing for using a pyglet group to manage OpenGL state.
     If no pyglet group is given, pyglet.graphics.NullGroup() will be used.
     postdraw()
          Called after calling the draw() Method.
          Useful for unsetting OpenGL state.
     predraw()
          Called before calling the draw () Method.
          Useful for setting up OpenGL state.
class peng3d.gui.layered.ImageWidgetLayer(name, widget, z_index=None, border=[0, 0],
                                                        offset=[0, 0], img=[None, None])
     Subclass of WidgetLayer() implementing a simple static image view.
     This layer can display any resource representable by the ResourceManager ().
     img is a 2-tuple of (resource_name, category).
     The z index for this Layer defaults to 1.
     initialize()
          Called just before on redraw() is called the first time.
     on redraw()
          Called when the Layer should be redrawn.
          If a subclass uses the initialize() Method, it is very important to also call the Super Class Method
          to prevent crashes.
class peng3d.qui.layered.DynImageWidgetLayer(name, widget, z_index=None, border=[0,
                                                            0], offset=[0, 0], imgs=\{\}, default=None)
     Subclass of WidgetLayer allowing for dynamic images.
     imgs is a dictionary of names to 2-tuples of (resource_name, category).
     If no default image name is given, a semi-random one will be selected.
     The z_index for this Layer defaults to 1.
     addImage (name, rsrc)
          Adds an image to the internal registry.
          rsrc should be a 2-tuple of (resource_name, category).
     initialize()
          Called just before on redraw() is called the first time.
     on redraw()
          Called when the Layer should be redrawn.
          If a subclass uses the initialize() Method, it is very important to also call the Super Class Method
          to prevent crashes.
```

switchImage (name)

Switches the active image to the given name.

Raises ValueError – If there is no such image

Subclass of DynImageWidgetLayer allowing for dynamically smart scaled images.

Similar to FramedImageButton. Allows for scaling and/or repeating the borders, corners and center independently.

Note that the tex_size parameter, if not given, will be derived from a random texture that has been given in imgs. Also note that the frame, scale, repeat_edge and repeat_center parameters are identical for all images.

initialize()

Called just before on_redraw() is called the first time.

on_redraw()

Called when the Layer should be redrawn.

If a subclass uses the <code>initialize()</code> Method, it is very important to also call the Super Class Method to prevent crashes.

Subclass of ${\it DynImageWidgetLayer}$ () that acts like an ${\it ImageButton}$ ().

The img_* arguments are of the same format as in DynImageWidgetLayer().

This class internally uses the BasicWidget.getState() method for getting the state of the widget.

Subclass of WidgetLayer () displaying arbitrary plain text.

Note that this method internally uses a pyglet Label that is centered on the Layer.

The z_index for this Layer defaults to 2.

label

Property for accessing the text of the label.

on redraw(dt=None)

Called when the Layer should be redrawn.

If a subclass uses the initialize() Method, it is very important to also call the Super Class Method to prevent crashes.

redraw_label()

Re-draws the text by calculating its position.

Currently, the text will always be centered on the position of the layer.

Subclass of WidgetLayer() serving as a base class for other formatted label layers.

The Label Type can be set via the class attribute cls, it should be set to any class that is compatible with pyglet.text.Label.

It is recommended to use one of the subclasses of this class instead of this class directly.

The z_index for this Layer defaults to 2.

label

Property for accessing the text of the label.

Note that depending on the type of format, this property may not exactly represent the original text as it is converted internally.

on redraw(dt=None)

Called when the Layer should be redrawn.

If a subclass uses the initialize() Method, it is very important to also call the Super Class Method to prevent crashes.

redraw_label()

Re-draws the text by calculating its position.

Currently, the text will always be centered on the position of the layer.

```
class peng3d.gui.layered.HTMLLabelWidgetLayer(name, widget, z_index=None, border=[0, 0], offset=[0, 0], label=", font_size=None, font=None, font_color=None, multiline=False, style=None)
```

Subclass of FormattedLabelWidgetLayer implementing a basic HTML Label.

Note that not all tags are supported, see the docs for pyglet.text.HTMLLabel for details.

Subclass of WidgetLayer that displays a basic border around the layer.

Note that not all styles will look good with this class, see <code>ButtonBorderWidgetLayer()</code> for more information.

Note that the border and offset arguments have been renamed to base_border and base_offset to prevent naming conflicts.

Subclasses may set the n_vertices value to change the number of vertices or change_on_press to change the default value for the argument of the same name. By default, 36 vertices are used and changed_on_press is set to True.

The z_index for this Layer defaults to 0.5.

addStyle (name, func)

Adds a style to the layer.

Note that styles must be registered separately for each layer.

```
name is the (string) name of the style.
```

func will be called with its arguments as (bg,o,i,s,h), see getColors() for more information.

genVertices()

Called to generate the vertices used by this layer.

The length of the output of this method should be three times the n_vertices attribute.

See the source code of this method for more information about the order of the vertices.

getColors()

Overrideable function that generates the colors to be used by various styles.

Should return a 5-tuple of (bg, o, i, s, h).

bg is the base color of the background.

o is the outer color, it is usually the same as the background color.

i is the inner color, it is usually lighter than the background color.

s is the shadow color, it is usually quite a bit darker than the background.

h is the highlight color, it is usually quite a bit lighter than the background.

The returned values may also be statically overridden by setting the color_attribute to anything but None.

initialize()

Called just before on_redraw() is called the first time.

is hovering

Read-only helper property to be used by styles for determining if the layer should be rendered as hovered or not.

Note that this property may not represent the actual hovering state, it will always be False if change_on_press is disabled.

on_redraw()

Called when the Layer should be redrawn.

If a subclass uses the <code>initialize()</code> Method, it is very important to also call the Super Class Method to prevent crashes.

pressed

Read-only helper property to be used by styles for determining if the layer should be rendered as pressed or not.

Note that this property may not represent the actual pressed state, it will always be False if change_on_press is disabled.

stretchColors(c)

Method that is called to stretch the colors.

Note that this should be implemented by subclasses if plausible and reasonable.

Subclass of BaseBorderWidgetLayer() implementing Button-Style borders.

This class is based on the ButtonBackground class. This means that most styles are also available here and should look identical.

Note that this class uses only 20 vertices and is thus not compatible with styles created for use with BaseBorderWidgetLayer.

Also note that the border argument also only receives two values instead of eight.

genVertices()

Called to generate the vertices used by this layer.

The length of the output of this method should be three times the n_vertices attribute.

See the source code of this method for more information about the order of the vertices.

stretchColors(c)

Method that is called to stretch the colors.

Note that this should be implemented by subclasses if plausible and reasonable.

2.11 peng3d.gui.container - GUI Container and Scrolling system

Main class of the container system.

This widget may contain other widgets, limiting the childs to only draw within the defined bounds. Additionally, the given position will also act as a offset, making the child coordinates relative to the parent.

The visible attribute may be set to control whether or not this container is visible.

This Class is a subclass of peng3d.gui.widgets.Widget but also exhibits part of the API of peng3d.gui.SubMenu.

addWidget (widget, order_key=0)

Adds a widget to this container.

Note that trying to add the Container to itself will be ignored.

clickable

Property used for determining if the widget should be clickable by the user.

This is only true if the submenu of this widget is active and this widget is enabled.

The widget may be either disabled by setting this property or the enabled attribute.

draw()

Draws the submenu and its background.

Note that this leaves the OpenGL state set to 2d drawing and may modify the scissor settings.

getWidget (name)

Returns the widget with the given name.

on_enter(old)

Dummy method defined for compatibility with peng3d.gui.SubMenu, simply does nothing.

on_exit(new)

Dummy method defined for compatibility with peng3d. qui. SubMenu, simply does nothing.

on redraw()

Redraws the background and any child widgets.

redraw()

Triggers a redraw of the widget.

Note that the redraw may not be executed instantly, but rather batched together on the next frame. If an instant and synchronous redraw is needed, use on_redraw() instead.

setBackground(bg)

Sets the background of the Container.

Similar to peng3d.gui.SubMenu.setBackground(), but only effects the region covered by the Container.

class peng3d.gui.container.ScrollableContainer(name: Optional[str], submenu: Sub-

Menu, window: Any = None, peng: Any = None, *, pos: Union[List[float], Callable[[float, float, float, float], Tuple[float, float]], layout.LayoutCell], size: Union[List[float], Callable[[float, float], Tuple[float, float]], None] = None, scrollbar_width=12, font=None, font_size=None, font_color=None, borderstyle=None, content_height=100)

Subclass of Container allowing for scrolling its content.

The scrollbar currently is always on the right side and simply consists of a peng3d.gui.slider. VerticalSlider.

scrollbar_width and borderstyle will be passed to the scrollbar.

content_height refers to the maximum offset the user can scroll to.

The content height may be changed, but manually calling redraw() will be necessary.

on redraw()

Redraws the background and contents, including scrollbar.

This method will also check the scrollbar for any movement and will be automatically called on movement of the slider.

Background class used to render the background of containers using a button style.

Mostly identical with ButtonBackground with added compatibility for containers.

getColors()

Overrideable function that generates the colors to be used by various borderstyles.

Should return a 5-tuple of (bg, o, i, s, h).

bg is the base color of the background.

o is the outer color, it is usually the same as the background color.

i is the inner color, it is usually lighter than the background color.

s is the shadow color, it is usually quite a bit darker than the background.

h is the highlight color, it is usually quite a bit lighter than the background.

2.12 peng3d.gui.text - Textual Widgets

Simple widget that can display any single-line non-formatted string.

This widget does not use any background by default.

The default font color is chosen to work on the default background color and may need to be changed if the background color is changed.

label

Property for accessing the text of the label.

on_redraw(dt=None)

Draws the background and the widget itself.

Subclasses should use super () to call this method, or rendering may glitch out.

redraw_label()

Re-draws the text by calculating its position.

Currently, the text will always be centered on the position of the label.

Basic Textual Input widget.

By default, this widget uses TextInputBackground as its Background class.

The optional default text will only be displayed if the text is empty.

The allow_overflow flag determines if the text entered can be longer than the size of the TextInput.

The allow_copypaste flag controls whether or not the user can copy and paste the contents of the text box. By default, copying and pasting is allowed. This flag can also be set to "force" to force a crash with an appropriate error message if the pyperclip module is not available. Currently, only copying, pasting and cutting the whole text box is supported, as there is no mechanism for text selection yet.

The key combinations used by this widget can be configured in the config via the controls.keybinds.common.* config values.

parent_bgcls may be used to override the background used. Note that the cursor will still be rendered. Additional parameters required by the custom background should be passed as keyword arguments. Note that arguments already used by TextInput are not passed down. This may cause issues with ButtonBackground and some other classes.

allow_returnkey determines whether pressing the return key inserts a \r character or not. Note that the send_form action of the submenu may still be sent, even if this is set to true.

default

Property for accessing the default text.

draw()

Draws all vertex lists associated with this widget.

on redraw()

Draws the background and the widget itself.

Subclasses should use super () to call this method, or rendering may glitch out.

redraw_label()

Re-draws the label by calculating its position.

Currently, the label will always be centered on the position of the label.

text

Property for accessing the text.

```
class peng3d.gui.text.TextInputBackground(*args, **kwargs)
```

Background for the TextInput Widget.

This background uses the button drawing routines and adds a cursor.

init_bg()

Called just before the background will be drawn the first time.

Commonly used to initialize vertex lists.

It is recommended to add all vertex lists to the submenu.batch2d Batch to speed up rendering and preventing glitches with grouping.

pressed

Read-only helper property to be used by borderstyles for determining if the widget should be rendered as pressed or not.

Note that this property may not represent the actual pressed state, it will always be False if change_on_press is disabled.

redraw_bg()

Method called by the parent widget every time its Widget.redraw() method is called.

*args, **kwargs)

Background for the TextInput Widget.

This background adds a cursor on top of another background.

init_bg()

Called just before the background will be drawn the first time.

Commonly used to initialize vertex lists.

It is recommended to add all vertex lists to the submenu.batch2d Batch to speed up rendering and preventing glitches with grouping.

redraw_bg()

Method called by the parent widget every time its Widget .redraw() method is called.

```
class peng3d.gui.text.PasswordInput(*args, replacement_char='*', **kwargs)
```

password

Proxy for text.

Returns Current password

text

Property for accessing the text.

2.13 peng3d.gui.slider - Slider and Progressbar Widgets

Progressbar displaying a progress of any action to the user.

By default, this Widget uses ProgressbarBackground as its Background class.

The border and borderstyle options are the same as for the peng3d.gui.button.Button Widget.

The two colors given are for left and right, respectively. This may be used to create gradients.

nmin, nmax and n represent the minimal value, maximal value and current value, respectively. Unexpected behavior may occur if the minimal value is bigger then the maximum value.

n

Property representing the current value of the progressbar.

Changing this property will activate the progresschange action.

nmax

Property representing the maximum value of the progressbar. Typically 100 to represent percentages easily.

nmin

Property representing the minimal value of the progressbar. Typically 0.

value

Alias to the *n* property.

```
class peng3d.gui.slider.ProgressbarBackground (widget, border, borderstyle, colors)
Background for the Progressbar Widget.
```

This background displays a bar with a border similar to ButtonBackground. Note that two colors may be given, one for the left and one for the right.

init bq()

Called just before the background will be drawn the first time.

Commonly used to initialize vertex lists.

It is recommended to add all vertex lists to the submenu.batch2d Batch to speed up rendering and preventing glitches with grouping.

redraw_bg()

Method called by the parent widget every time its Widget .redraw() method is called.

class peng3d.gui.slider.AdvancedProgressbar(name: Optional[str], submenu: SubMenu,

window: Any = None, peng: Any = None, *, pos: Union[List[float], Callable[[float, float, float], Tuple[float, float]], layout.LayoutCell], size: Union[List[float], Callable[[float, float], Tuple[float, float]], None] = None, bg=None, categories=None, offset_nmin=0, offset_nmax=0, offset_n=0, border=None, borderstyle=None, colors=[[240, 119, 70], [240, 119, 70]])

Advanced Progressbar displaying the combined progress through multiple actions.

Visually, this widget is identical to *Progressbar* with the only difference being the way the progress percentage is calculated.

The offset_nmin, offset_n and offset_nmax parameters are equivalent to the parameters of the same name minus the offset prefix.

categories may be any dictionary mapping category names to 3-tuples of format (nmin, n, nmax).

It is possible to read, write and delete categories through the widget [cat] syntax. Note however, that modifying categories in-place, e.g. like widget [cat] [1] = 100, requires a manual call to redraw().

When setting the *nmin*, *n* or *nmax* properties, only an internal offset value will be modified. This may result in otherwise unexpected behavior if setting e.g. n to nmax because the categories may influence the total percentage calculation.

addCategory (name, nmin=0, n=0, nmax=100)

Adds a category with the given name.

If the category already exists, a KeyError will be thrown. Use <code>updateCategory()</code> instead if you want to update a category.

deleteCategory (name)

Deletes the category with the given name.

If the category does not exist, a KeyError will be thrown.

n

Property representing the current value of the progressbar.

Changing this property will activate the progresschange action.

nmax

Property representing the maximum value of the progressbar. Typically 100 to represent percentages easily.

nmin

Property representing the minimal value of the progressbar. Typically 0.

updateCategory (name, nmin=None, n=None, nmax=None)

Smartly updates the given category.

Only values that are given will be updated, others will be left unchanged.

If the category does not exist, a KeyError will be thrown. Use addCategory() instead if you want to add a category.

Slider that can be used to get a number from the user.

By default, this Widget uses SliderBackground as its Background class.

Most options are the same as for *Progressbar*.

handlesize simply determines the size of the handle.

Note that scaling this widget on the y-axis will not do much, scale the handlesize instead.

р

Helper property containing the percentage this slider is "filled".

This property is read-only.

Background for the Slider Widget.

This background displays a button-like handle on top of a bar representing the selectable range.

All given parameters will affect the handle.

getPosSize()

Helper function converting the actual widget position and size into a usable and offsetted form.

This function should return a 6-tuple of (sx, sy, x, y, bx, by) where sx and sy are the size, x and y the position and bx and by are the border size.

All values should be in pixels and already include all offsets, as they are used directly for generation of vertex data.

This method can also be overridden to limit the background to a specific part of its widget.

init_bg()

Called just before the background will be drawn the first time.

Commonly used to initialize vertex lists.

It is recommended to add all vertex lists to the submenu.batch2d Batch to speed up rendering and preventing glitches with grouping.

redraw bq()

Method called by the parent widget every time its Widget.redraw() method is called.

Vertical slider that can be used as a scrollbar or getting other input.

By default, this Widget uses VerticalSliderBackground as its Background class.

This widget is essentially the same as Slider, only vertical.

Note that you may need to flip the x and y values of size, handlesize and border compared to Slider.

Background for the VerticalSlider Widget.

This background uses the same technique as SliderBackground, simply turned by 90 Degrees.

getPosSize()

Helper function converting the actual widget position and size into a usable and offsetted form.

This function should return a 6-tuple of (sx, sy, x, y, bx, by) where sx and sy are the size, x and y the position and bx and by are the border size.

All values should be in pixels and already include all offsets, as they are used directly for generation of vertex data.

This method can also be overridden to limit the background to a specific part of its widget.

2.14 peng3d.gui.style - Generic Styles for Widgets

```
class peng3d.gui.style.Borderstyle
```

Base class for all border styles.

Each border style class serves a single style, although some parameters may be adjustable.

Currently, border style classes are not instantiated per widget, but rather rely on class methods. This reduces memory overhead but may be changed in the future.

For backwards compatibility, border style classes themselves compare equal with their old-style string equivalents. This is accomplished with a metaclass and not necessary to emulate for new styles and may be removed in a future version.

TODO: document return format

Parameters

- widget (BasicWidget) Widget that the color map belongs to
- **bg** (ColorRGB) Background color this widget is placed on
- o (ColorRGB) Outer color, usually same as the background
- i (ColorRGB) Inner color, usually lighter than the background
- **s** (ColorRGB) Shadow color, usually quite a bit darker than the background
- h (ColorRGB) Highlight color, usually quite a bit lighter than the background
- **state** (*str*) Optional widget state override

Returns

Return type

```
class peng3d.gui.style.FlatBorder
```

```
classmethod get_colormap (widget: widgets.BasicWidget, bg: List[int], o: List[int], i: List[int], s: List[int], h: List[int], state: Optional[str] = None)

Gets the color map for a button-style widget.
```

TODO: document return format

Parameters

- ullet widget (BasicWidget) Widget that the color map belongs to
- **bg** (ColorRGB) Background color this widget is placed on
- o (ColorRGB) Outer color, usually same as the background
- i (ColorRGB) Inner color, usually lighter than the background
- **s** (ColorRGB) Shadow color, usually quite a bit darker than the background
- h (ColorRGB) Highlight color, usually quite a bit lighter than the background
- **state** (str) Optional widget state override

Returns

Return type

class peng3d.gui.style.GradientBorder

classmethod get_colormap (widget: widgets.BasicWidget, bg: List[int], o: List[int], i: List[int], s: List[int], h: List[int], state: Optional[str] = None)

Gets the color map for a button-style widget.

TODO: document return format

Parameters

- widget (BasicWidget) Widget that the color map belongs to
- **bg** (ColorRGB) Background color this widget is placed on
- o (ColorRGB) Outer color, usually same as the background
- i (ColorRGB) Inner color, usually lighter than the background
- **s** (ColorRGB) Shadow color, usually quite a bit darker than the background
- h (ColorRGB) Highlight color, usually quite a bit lighter than the background
- **state** (str) Optional widget state override

Returns

Return type

class peng3d.gui.style.OldshadowBorder

classmethod get_colormap (widget: widgets.BasicWidget, bg: List[int], o: List[int], i: List[int], s: List[int], h: List[int], state: Optional[str] = None)

Gets the color map for a button-style widget.

TODO: document return format

Parameters

- widget (BasicWidget) Widget that the color map belongs to
- bg(ColorRGB) Background color this widget is placed on
- o (ColorRGB) Outer color, usually same as the background
- i (ColorRGB) Inner color, usually lighter than the background

- **s** (ColorRGB) Shadow color, usually quite a bit darker than the background
- h (ColorRGB) Highlight color, usually quite a bit lighter than the background
- **state** (str) Optional widget state override

Returns

Return type

class peng3d.qui.style.MaterialBorder

```
classmethod get_colormap (widget: widgets.BasicWidget, bg: List[int], o: List[int], i: List[int], s: List[int], h: List[int], state: Optional[str] = None)

Gets the color map for a button-style widget.
```

TODO: document return format

Parameters

- \bullet widget (BasicWidget) Widget that the color map belongs to
- **bg** (ColorRGB) Background color this widget is placed on
- o (ColorRGB) Outer color, usually same as the background
- i (ColorRGB) Inner color, usually lighter than the background
- **s** (ColorRGB) Shadow color, usually quite a bit darker than the background
- h (ColorRGB) Highlight color, usually quite a bit lighter than the background
- **state** (*str*) Optional widget state override

Returns

Return type

See the documentation of each class for descriptions.

```
peng3d.gui.style.norm_borderstyle (borderstyle: Union[str, Type[peng3d.gui.style.Borderstyle]])

Type[peng3d.gui.style.Borderstyle]

Normalizes border styles to Borderstyle subclasses.
```

Parameters borderstyle (Either str or Borderstyle subclass) - Value to normalize

Returns Normalized value

Return type Borderstyle subclass

Raises TypeError – if an unexpected value was given

Core of the hierarchical style system.

This class allows for easily inheriting styles from a parent (e.g. submenu or menu) while allowing dynamic overwriting at any level in the hierarchy. For example, a specific submenu could have a different font that would then be automatically applied to all widgets within it, unless the font was overridden for the widget locally.

When reading a style attribute, this class first checks if it has a local override for that attribute. If so, it will be returned. If the attribute wasn't overridden locally, the parent is queried and its result returned. The root of this

hierarchy is the style attribute of the *Peng()* singleton, which uses the styles defined in *DEFAULT_STYLE* as a default. If a style attribute is not found anywhere, a KeyError will be raised.

When writing a style attribute, a local override is created. This causes all subsequent accesses to the style attribute within this instance and all children (e.g. widgets within a submenu) to read back the new value. Deleting the style attribute will reset this override and thus reset the read value back to the parent value.

Note that changes in an attribute usually require a redraw of the affected widgets. If a redraw is not performed, weird graphical glitches may happen.

This class is very flexible and allows several different modes of access.

First, it is possible to use it like a dict, e.g. style["font"]. It is possible to read, write and delete using this method. All styles are accessible in this manner and arbitrary strings are allowed as keys, though it is recommended to stick to valid Python identifiers.

For convenience, it is also possible to access style attributes as literal attributes of a <code>Style</code> instance, e.g. <code>style.font</code>. Note that this only allows accesses to style attributes whose name is a valid python identifier and that are not in the list of reserved attributes, stored in the class attribute <code>Style.ATTRIBUTES</code>. It is also not possible to access style attributes that start with an underscore or are methods of <code>Style</code> this way. This access mode also supports read, write and delete accesses.

Note that unlike the helpers default_property and default, Style does not reset an override if a write with a value of None is performed.

ATTRIBUTES = ['parent', 'ATTRIBUTES']

Internal list of attributes that are reserved and cannot be used for styles via attribute access.

This list may be extended in the future. Note that all attributes that start with an underscore are also implicitly reserved.

add_watcher (watch_sel, callback=None)

Adds a watcher for specific changes in local styles.

Watchers can be used to automatically update widgets or other visual elements whenever the effective value of a style attribute changes. This includes scenarios where the (not locally overridden) style attribute of the parent changes, causing a change in the effective local value.

The watcher system tries its best to remove unnecessary triggers and double-triggers, but they may still occur under some circumstances. Thus, it is recommended to only use (semi-)idempotent functions as callbacks. A popular example for a suitable callback would be the *redraw()* method of widgets, since it will only queue the actual redraw and thus prevents extraneous redraws.

This method accepts either an instance of StyleWatcher or a selector string followed by a callback function.

Selectors are strings that describe what changes to listen to. Currently, selectors are quite rudimentary, but it is planned to add a more sophisticated system later.

The special * selector matches all changes and will thus be triggered on any change of any local attribute.

Alternatively, all other strings will trigger on the change of a style attribute with their exact name.

Callback functions can either take no arguments or the old value of the style attribute as a single argument.

get (key: str, default: Union[float, str, Type[Borderstyle], None] = None) → Union[float, str, Type[peng3d.gui.style.Borderstyle], None]
Returns the effective value of the given key or the given default if it couldn't be found.

$is_overridden(key: str) \rightarrow bool$

Checks whether a given key is currently being overridden.

If this returns true, any change in parent styles will not affect the value of the given style attribute.

Parameters key(str) – Key to check

Returns whether key is currently overridden

Return type bool

 $override_if_not_none(key: str, value: Union[float, str, Type[Borderstyle], None]) \rightarrow None$ Overrides the given key if the provided value is not None.

This helper allows for easy style overriding via keyword arguments. Simply create a keyword argument in the constructor of an object that uses styles and set the default of that keyword argument to None. In the constructor, you can then call this function like so:

```
self.style.override_if_not_none("font", font)
```

Note that this method is unsuitable for style attributes that may actually want to have a value of None.

Parameters

- **key** (str) Key to override
- value (Optional [StyleValue]) value used to override if it is not None

Returns None

Return type None

parent = None

Attribute that stores the parent of this style.

May be changed during runtime, though most widgets will require a redraw to fully respect changed effective style values.

It is usually not required to write to this attribute, since widgets do not currently support being moved between different submenus or even menus.

```
update (\_overrides: Optional[Dict[str, Union[float, str, Type[Borderstyle]]]] = None, **kwargs) <math>\rightarrow
      Updates several style attributes at the same time.
```

Note that this method only supports creating and modifying overrides. Keys not present in the given data will be kept as is.

This method supports both passing in a dictionary and passing in keyword attributes. Note that in the case of a style attribute being present in both the dictionary and a keyword argument, the keyword argument takes precedence.

Parameters

- _overrides (Optional[Dict[str, StyleValue]]) Optional dictionary to add/modify overrides from
- **kwarqs** (StyleValue) Optional keyword arguments to add/modify overrides from

Returns None

Return type None

```
peng3d.qui.style.DEFAULT_STYLE = {'border': (4, 4), 'borderstyle': <class 'peng3d.qui.style': <class '
                                                                          Default styles for all parts of peng3d.
```

These styles represent a sensible default for common use cases.

For application-wide changes, it is recommended to override the styles in question using the peng3d.peng. Peng.style attribute.

2.15 peng3d.resource - Resource loading system

class peng3d.resource.ResourceManager (peng: peng3d.Peng, basepath: str)

Manager that allows for efficient and simple loading and management of different kinds of resources.

Currently supports textures and models out of the box, but extension is possible.

Textures can be queried by any part of the application, they are only loaded on the first request and then cached for every request following it.

The same caching and lazy-loading principle applies to models loaded via this system.

 $addCategory(name: str, size: Optional[int] = None) \rightarrow int$

Adds a new texture category with the given name.

If the category already exists, it will be overridden.

addFromTex (name: str, img: <Mock name='mock.AbstractImage' id='139691013134096'>, category: str) → Tuple[int, int, Tuple]

Adds a new texture from the given image.

img may be any object that supports Pyglet-style copying in form of the blit_to_texture() method.

This can be used to add textures that come from non-file sources, e.g. Render-to-texture.

getMissingTexture() → <Mock name='mock.AbstractImage' id='139691013134096'>

Returns a texture to be used as a placeholder for missing textures.

A default missing texture file is provided in the assets folder of the source distribution. It consists of a simple checkerboard pattern of purple and black, this image may be copied to any project using peng3d for similar behavior.

If this texture cannot be found, a pattern is created in-memory, simply a solid square of purple.

This texture will also be cached separately from other textures.

getModel (name: str) → peng3d.model.Model

Gets the model object by the given name.

If it was loaded previously, a cached version will be returned. If it was not loaded, it will be loaded and inserted into the cache.

```
getModelData(name: str) \rightarrow Dict[KT, VT]
```

Gets the model data associated with the given name.

If it was loaded, a cached copy will be returned. It it was not loaded, it will be loaded and cached.

 $getTex(name: str, category: str) \rightarrow Tuple[int, int, Tuple]$

Gets the texture associated with the given name and category.

category must have been created using addCategory() before.

If it was loaded previously, a cached version will be returned. If it was not loaded, it will be loaded and inserted into the cache.

See *loadTex()* for more information.

 $\textbf{loadModel} \ (\textit{name: str}) \ \rightarrow \texttt{peng3d.model.Model}$

Loads the model of the given name.

The model will also be inserted into the cache.

 $loadModelData(name: str) \rightarrow Dict[KT, VT]$

Loads the model data of the given name.

The model file must always be a .json file.

loadTex (*name: str, category: str*) \rightarrow Tuple[int, int, Tuple]

Loads the texture of the given name and category.

All textures currently must be PNG files, although support for more formats may be added soon.

If the texture cannot be found, a missing texture will instead be returned. See getMissingTexture()
for more information.

Currently, all texture mipmaps will be generated and the filters will be set to GL_NEAREST for the magnification filter and GL_NEAREST_MIPMAP_LINEAR for the minification filter. This results in a pixelated texture and not a blurry one.

```
resourceExists (name: str, ext: str = ") \rightarrow bool
```

Returns whether or not the resource with the given name and extension exists.

This must not mean that the resource is meaningful, it simply signals that the file exists.

```
resourceNameToPath (name: str, ext: str = ") \rightarrow str
```

Converts the given resource name to a file path.

A resource path is of the format <app>:<cat1>.<cat2>.<name> where cat1 and cat2 can be repeated as often as desired.

ext is the file extension to use, e.g. .png or similar.

As an example, the resource name peng3d: some.category.foo with the extension.png results in the path
 /assets/peng3d/some/category/foo.png.

This resource naming scheme is used by most other methods of this class.

Note that it is currently not possible to define multiple base paths to search through.

2.16 peng3d.i18n - Lightweight Translation Manager

class peng3d.i18n.TranslationManager(peng: peng3d.Peng)

Manages sets of translation files in multiple languages.

This Translation System uses language codes to identify languages, there is no requirement to follow a specific standard, but it is recommended to use simple 2-digit codes like en and de, adding an underscore to define sub-languages like en_gb and en_us.

Whenever a new translation file is needed, it will be parsed and then cached. This speeds up access times and also practically eliminates load times when switching languages.

Several events are sent by this class, see *peng3d:i18n.* Events Category*.

Most of these events are also sent as actions, these actions are described in the methods that cause them.

There are also severale config options that determine the behaviour of this class. See *Translation Options* for more information.

This Manager requires the ResourceManager () to be already initialized.

```
discoverLangs(domain: str = '*') \rightarrow List[str]
```

Generates a list of languages based on files found on disk.

The optional domain argument may specify a domain to use when checking for files. By default, all domains are checked.

This internally uses the glob built-in module and the i18n.lang.format config option to find suitable filenames. It then applies the regex in i18n.discover_regex to extract the language code.

 $\textbf{loadDomain} (domain: str, lang: Optional[str] = None, encoding: str = 'utf-8') \rightarrow bool$

Loads the translation data of a single domain for a specific language from disk into the cache.

If no language was given, the current language is used.

If the translation file could not be found or any errors occur while reading it, these errors will be silently discarded, only recognizable by a return value of False.

If the load was successful, the action loaddomain will be executed and this method will return True.

```
setLang(lang: str) \rightarrow None
```

Sets the default language for all domains.

For recommendations regarding the format of the language code, see TranslationManager.

Note that the lang parameter of both translate() and translate_lazy() will override this setting.

Also note that the code won't be checked for existence or plausibility. This may cause the fallback strings to be displayed instead if the language does not exist.

Calling this method will cause the setlang action and the :peng3d:event'peng3d:i18n.set_lang' event to be triggered. Note that both action and event will be triggered even if the language did not actually change.

This method also automatically updates the i18n.lang config value.

t (*key: str, translate: bool = True, lang: Optional[str] = None*) \rightarrow str Translates the given key.

If no language was given, the language last passed to setLang() will be used.

If the translation key could not be found (e.g. because the language code is invalid), the key itself will be returned.

Note that this method returns a string and thus does not have any way to modify the returned value if the language is changed by the user. If dynamic translation is required, <code>translate_lazy()</code> should be used instead.

t1 (key: str, data: Optional[Dict[KT, VT]] = None, translate: bool = True, lang: Optional[str] = None)

→ peng3d.i18n._LazyTranslator
Lazily translates a given translation key.

This method is similar to translate(), but returns a special object rather than a string. This allows for on-the-fly changing of the language without having to re-set all the places where translated strings are used.

Whenever the returned object is converted to a string by str() or repr() or is formatted using either the old %-notation or the newer str.format(), the translation key will be looked up again, in case the language has changed.

Note that this requires support from the widgets (or other consumers of the returned value), namely that they only convert to string just prior to rendering and re-render either regularly or whenever either the setlang action or the peng3d:i18n.set_lang event is called.

Most built-in widgets support this, but some special cases are not supported yet. For example, setting the window title dynamically requires using the caption_t parameter instead of the raw caption parameter.

translate (*key: str, translate: bool* = True, $lang: Optional[str] = None) <math>\rightarrow$ str Translates the given key.

If no language was given, the language last passed to setLang() will be used.

If the translation key could not be found (e.g. because the language code is invalid), the key itself will be returned.

Note that this method returns a string and thus does not have any way to modify the returned value if the language is changed by the user. If dynamic translation is required, <code>translate_lazy()</code> should be used instead.

```
translate_lazy (key: str, data: Optional[Dict[KT, VT]] = None, translate: bool = True, lang: Optional[str] = None) \rightarrow peng3d.i18n._LazyTranslator Lazily translates a given translation key.
```

This method is similar to translate(), but returns a special object rather than a string. This allows for on-the-fly changing of the language without having to re-set all the places where translated strings are used.

Whenever the returned object is converted to a string by str() or repr() or is formatted using either the old %-notation or the newer str.format(), the translation key will be looked up again, in case the language has changed.

Note that this requires support from the widgets (or other consumers of the returned value), namely that they only convert to string just prior to rendering and re-render either regularly or whenever either the setlang action or the peng3d:i18n.set_lang event is called.

Most built-in widgets support this, but some special cases are not supported yet. For example, setting the window title dynamically requires using the caption_t parameter instead of the raw caption parameter.

2.17 peng3d.model - Model and Animation system

```
peng3d.model.grouper(iterable, n, fillvalue=None)
```

Allows for iteration over multiple elements of a iterable at once.

iterable may be any iterable, its values will be returned. Note that this may be iterated over more than once.

n is the size of each group. May be any positive integer.

fillvalue is optionally used to fill any groups that do not have enough items, for example if the length of the iterable is not divisible by n.

Example:

```
>>> for i in grouper("foobarbaz",2,fillvalue=" "):
... print(i)
fo
ob
ar
ba
z # Note the extra space after the z
```

peng3d.model.calcSphereCoordinates (pos, radius, rot)

Calculates the Cartesian coordinates from spherical coordinates.

pos is a simple offset to offset the result with.

radius is the radius of the input.

```
rot is a 2-tuple of (azimuth, polar) angles.
```

Angles are given in degrees. Most directions in this game use the same convention.

The azimuth ranges from 0 to 360 degrees with 0 degrees pointing directly to the x-axis.

The polar angle ranges from -90 to 90 with -90 degrees pointing straight down and 90 degrees straight up.

A visualization of the angles required is given in the source code of this function.

peng3d.model.v magnitude(v)

Simple vector helper function returning the length of a vector.

v may be any vector, with any number of dimensions

```
peng3d.model.v_normalize(v)
```

Normalizes the given vector.

The vector given may have any number of dimensions.

```
class peng3d.model.Material(rsrcMgr, name, matdata)
```

Object that describes a single material of a model.

This object stores all relevant data and caches. Note that this object is only created once for each model and shared between all rendered instances of it.

See Model for more information about the model system.

id

Read-only property storing the numerical ID of the texture of this material.

Used to manipulate the texture behind this material.

Commonly used in binding the texture: glBindTexture (material.target, material.id).

target

Read-only property storing the OpenGL constant representing the target of the texture of this material.

Commonly GL_TEXTURE_2D or GL_TEXTURE_3D.

Used in texture manipulation and activation, e.g. glEnable (material.target).

tex_coords

Read-only property storing the texture coordinates to use when drawing with this texture.

Should not be used directly, see transformTexCoords().

Enables substitution of pyglet pyglet.graphics.Texture objects with Materials in many places, e.g. in pyglet.graphics.TextureGroup.

texdata

Read-only property equivalent to a 3-tuple containing target, id and tex_coords.

Should be faster than getting each value directly. Useful if all of these values are needed.

transformTexCoords (data, texcoords, dims=2)

Transforms the given texture coordinates using the internal texture coordinates.

Currently, the dimensionality of the input texture coordinates must always be 2 and the output is 3-dimensional with the last coordinate always being zero.

The given texture coordinates are fitted to the internal texture coordinates. Note that values higher than 1 or lower than 0 may result in unexpected visual glitches.

The length of the given texture coordinates should be divisible by the dimensionality.

class peng3d.model.Bone(rsrcMgr, name, bonedata)

Object that represents a single bone of a model.

This object stores all relevant data and caches. Note that this object is only created once for each model and shared between all rendered instances of it.

Actual bone rotation and length is stored per entity and not per model allowing for different bone rotations for multiple entities using the same model.

See Model for more information about the model system.

addRegion (region)

Register a vertex Region as a dependent of this bone.

region must be an instance of Region.

ensureBones (data)

Helper method ensuring per-entity bone data has been properly initialized.

Should be called at the start of every method accessing per-entity data.

data is the entity to check in dictionary form.

getLength (data)

Returns the length of this bone in the given entity.

data is the entity to query in dictionary form.

getPivotPoint (data)

Returns the point this bone pivots around on the given entity.

This method works recursively by calling its parent and then adding its own offset.

The resulting coordinate is relative to the entity, not the world.

getRot (data)

Returns the rotation of this bone in the given entity.

data is the entity to query in dictionary form.

setLength (data, blength)

Sets the length of this bone on the given entity.

data is the entity to modify in dictionary form.

blength is the new length of the bone.

setParent (parent)

Sets the parent of this bone for all entities.

Note that this method must be called before many other methods to ensure internal state has been initialized.

This method also registers this bone as a child of its parent.

setRot (data, rot)

Sets the rotation of this bone on the given entity.

data is the entity to modify in dictionary form.

rot is the rotation of the bone in the format used in calcSphereCoordinates().

setRotate (data)

Sets the OpenGL state required for proper drawing of the model.

Mostly rotates and translates the camera.

It is important to call <code>unsetRotate()</code> after calling this method to properly unset state and avoid OpenGL errors.

transformVertices (data, vertices, dims=3)

Currently unused method that transforms the given vertices according to the rotation of the bone.

Currently just returns the vertices unmodified, will be implemented in the future.

unsetRotate (data)

Unsets the OpenGL state that was set before calling setRotate().

Note that this method may cause various OpenGL errors if called without <code>setRotate()</code> having been called.

class peng3d.model.RootBone (rsrcMgr, name, bonedata)

Special bone that represents the root of a entity.

This bone is immutable and cannot be rotated or otherwise modified.

getLength (data)

Returns the length of this bone in the given entity.

data is the entity to query in dictionary form.

getPivotPoint (data)

Returns the point this bone pivots around on the given entity.

This method works recursively by calling its parent and then adding its own offset.

The resulting coordinate is relative to the entity, not the world.

setRotate (data)

Sets the OpenGL state required for proper drawing of the model.

Mostly rotates and translates the camera.

It is important to call <code>unsetRotate()</code> after calling this method to properly unset state and avoid OpenGL errors.

unsetRotate(data)

Unsets the OpenGL state that was set before calling setRotate().

Note that this method may cause various OpenGL errors if called without setRotate() having been called.

class peng3d.model.Region(rsrcMgr, name, regdata)

Object that represents a vertex region of a model.

A vertex region is associated with a specific bone of the same model it is associated with. It has a list of vertices and optionally texture coordinates. The texture coordinates are transformed using the material it is associated with.

Most regions will use quads as their primitive type, but it is also possible to use triangles, lines and points.

To use quads as the geometry type, specify either quads, $quad or GL_QUADS$ as its $geometry_type$.

To use triangles as the geometry type, specify either tris, triangles, triangle or GL_TRIANGLES as its geometry type.

To use lines as the geometry type, specify either lines, line or GL_LINES as its geometry_type.

To use points as the geometry type, specify either points, point, dots, dot or GL_POINTS as its geometry_type.

Note that the number of vertices must be divisible by the number of vertices required per primitive, e.g. 4 for quads, 3 for triangles, 2 for lines and 1 for points.

Additionally, the number of vertices and texture coordinate pairs must also match.

If any of these conditions are not fulfilled, a ValueError will be raised.

getGeometryType (data)

Returns the OpenGL constant representing the type of primitives used by this region.

May be one of GL_QUADS, GL_TRIANGLES, GL_LINES or GL_POINTS.

getTexCoords (data)

Returns the texture coordinates, if any, to accompany the vertices of this region already transformed.

Note that it is recommended to check the enable_tex flag first.

Internally uses Material.transformTexCoords().

getTexInfo (data)

Returns informations about the texture of this region.

Internally uses Material.texdata, exact specification available there.

getVertices (data)

Returns the vertices of this region already transformed and ready-to-use.

Internally uses Bone.transformVertices().

class peng3d.model.Animation(rsrcMgr, name, anidata)

Object that represents an animation of a model.

Animations can be either static or animated using keyframes.

See Model for more information.

setBones (bones)

Sets the internal dictionary of bones in the parent model.

Must be a dictionary, else errors may appear later on.

startAnimation(data, jumptype)

Callback that is called to initialize this animation on a specific actor.

Internally sets the _anidata key of the given dict data.

jumptype is either jump or animate to define how to switch to this animation.

tickEntity(data)

Callback that should be called regularly to update the animation.

It is recommended to call this method about 60 times a second for smooth animations. Irregular calling of this method will be automatically adjusted.

This method sets all the bones in the given actor to the next state of the animation.

Note that startAnimation() must have been called before calling this method.

class peng3d.model.JSONModelGroup (model, data, obj, parent=None)

Pyglet group that sets the state required by a specific actor.

This group should always be set during any draw operations for the assigned actor. This can either be done by setting it as the group of a vertex list, the parent group of a group of a vertex list or manually calling set_state() and unset_state().

set_state()

Sets the state required for this actor.

Currently translates the matrix to the position of the actor.

unset_state()

Resets the state required for this actor to the default state.

Currently resets the matrix to its previous translation.

class peng3d.model.JSONRegionGroup (model, data, region, parent=None)

Pyglet group that manages the state required by a specific vertex region of an actor.

This group and the associated JSONModelGroup should always be set during any draw operation for the assigned region.

See JSONModelGroup for more information about how to do this.

set_state()

Sets the state required for this vertex region.

Currently binds and enables the texture of the material of the region.

unset_state()

Resets the state required for this actor to the default state.

Currently only disables the target of the texture of the material, it may still be bound.

class peng3d.model.Model(peng, rsrcMgr, name)

Object that represents the model of an actor.

Note that this object is not bound to an actor but rather to a collection of materials, bones, vertex regions and animations.

A single instance of this class may be used by multiple actors at the same time. See Actor.set Model() for more information.

A test model is available at assets/peng3d/model/test.json and a demo program using it under test_model.py.

Todo: Document the format of .json model files.

cleanup (obj)

Cleans up any left over data structures, including vertex lists that reside in GPU memory.

Behaviour is undefined if it is attempted to use this model with the same object without calling create() first.

It is very important to call this method manually during deletion as this will delete references to data objects stored in global variables of third-party modules.

create(obj, cache=False)

Initializes per-actor data on the given object for this model.

If cache is set to True, the entity will not be redrawn after initialization.

Note that this method may set several attributes on the given object, most of them starting with underscores.

During initialization of vertex regions, several vertex lists will be created. If the given object has an attribute called batch3d it will be used, else it will be created.

If the batch already existed, the draw() method will do nothing, else it will draw the batch.

Memory leaks may occur if this is called more than once on the same object without calling cleanup() first.

draw (obj)

Actually draws the model of the given object to the render target.

Note that if the batch used for this object already existed, drawing will be skipped as the batch should be drawn by the owner of it.

ensureModelData(obj)

Ensures that the given obj has been initialized to be used with this model.

If the object is found to not be initialized, it will be initialized.

redraw(obj)

Redraws the model of the given object.

Note that currently this method probably won't change any data since all movement and animation is done through pyglet groups.

remove(obj)

Called if the actor is removed from the world.

Can be extended for custom features, currently calls cleanup ().

setAnimation (*obj*, *animation*, *transition=None*, *force=False*)

Sets the animation to be used by the object.

See Actor.setAnimation() for more information.

2.18 peng3d.camera - Camera System

class peng3d.camera.Camera(world, name, pos=None, rot=None)

Camera object representing a location to draw from.

Each Camera object is bound to a world and has three properties: a name, pos and rot.

The name of the camera can be any string and is used to identify the camera and thus should be unique.

on activate (old)

Fake event handler called when this camera is made current by a WorldView() object.

on move (old, new)

Fake event handler called when this camera moves.

The old and new parameters are both 3D Locations and are not equal. Each parameter is a 3-tuple of (x, y, z) in world coordinates.

on_rotate(old, new)

Fake event handler called when this camera is rotated.

The old and new parameters are both rotations and are not equal. Each parameter is a 2-tuple of (yaw, pitch).

pos

Property for accessing the position of the camera.

This property uses a setter to call the <code>on_move()</code> method if set and the new location is not equal to the old location.

rot

Property for accessing the rotation of the camera.

This property uses a setter to call the $on_rotate()$ method if set and the new location is not equal to the old location.

class peng3d.camera.CameraActorFollower(world, name, actor)

Special Camera that follows the specified Actor().

Note that neither the <code>on_move()</code> nor the <code>on_rotate()</code> event handlers are called due to the way the updating works.

pos

This property always equals the value of self.actor.pos.

This property may also be written to.

rot

This property always equals the value of self.actor.rot.

This property may also be written to.

2.19 peng3d.world - World, Terrain and Actor management

class peng3d.world.World(peng)

World containing terrain, actors, cameras and views.

See the docs about Camera (), WorldView (), Actor () for more information about each class.

This class does not draw anything, see StaticWorld() for drawing simple terrain.

addActor (actor)

Adds the given actor to the internal registry.

Note that this actors unid attribute must be unique, else it will override any actors previously registered with its UUID.

addCamera (camera)

Add the camera to the internal registry.

Each camera name must be unique, or else only the most recent version will be used. This behavior should not be relied on because some objects may cache objects.

Additionally, only instances of Camera () may be used, everything else raises a TypeError.

addView (view)

Adds the supplied WorldView() object to the internal registry.

The same restrictions as for cameras apply, e.g. no duplicate names.

Additionally, only instances of WorldView () may be used, everything else raises a TypeError.

getView(name)

Returns the view with name name.

Raises a ValueError if the view does not exist.

render3d(view=None)

Renders the world in 3d-mode.

If you want to render custom terrain, you may override this method. Be careful that you still call the original method or else actors may not be rendered.

class peng3d.world.StaticWorld(peng, quads, colors)

Subclass of StaticWorld(), allows for semi-static terrain to be rendered.

This class is not suitable for highly complex or user-modifiable terrain.

quads is a list of 3d vertices, e.g. a single quad may be [-1,-1,-1, 1,-1,-1, 1,-1,1,-1,1], which represents a rectangle of size 2x2 centered around 0,0. It should also be noted that all quads have to be in a single list.

colors is a list of RGB Colors in a similar format to quads but with colors instead. Note that there must be a color for every vertex in the vertex list. Every color is an integer between 0 and 255 using the internal pyglet scheme c3B/static.

You can modify the terrain via the terrain attribute, note that it is a pyglet vertex list, and not a python list.

render3d(view=None)

Renders the world.

class peng3d.world.WorldView(world, name, cam)

Object representing a view on the world.

A WorldView () object references a camera and has a name.

cam is a valid camera name known to the world object supplied.

cam

Property for getting the currently active camera.

Always equals self.cameras[self.activeCamera].

on_menu_enter(old)

Fake event handler called by Layer.on_menu_enter() when the containing menu is entered.

on_menu_exit (new)

Fake event handler, same as on_menu_enter() but for exiting menus instead.

pos

Property for accessing the current position of the active camera.

The value of this property will always be a list of length 3.

This property can also be written to.

rot

Property for accessing the current rotation of the active camera.

This property can also be written to.

setActiveCamera (name)

Sets the active camera.

This method also calls the Camera.on_activate() event handler if the camera is not already active.

class peng3d.world.WorldViewMouseRotatable(world, name, cam)

Subclass of WorldView() that is rotatable using the user.

Moving the mouse cursor left or right will rotate the attached camera horizontally and moving the mouse cursor up or down will rotate the camera vertically.

By default, each pixel traveled changes the angle in degrees by 0.15, though this can be changed via the controls.mouse.sensitivity config value.

on key press (symbol, modifiers)

Keyboard event handler handling only the escape key.

If an escape key press is detected, mouse exclusivity is toggled via PengWindow. $toggle_exclusivity()$.

on_menu_enter(old)

Fake event handler, same as WorldView.on_menu_enter() but forces mouse exclusivity.

on_menu_exit(new)

Fake event handler, same as WorldView.on_menu_exit () but force-disables mouse exclusivity.

$on_{mouse_drag}(x, y, dx, dy, buttons, modifiers)$

Handler used to still enable mouse movement while a button is pressed.

on_mouse_motion (x, y, dx, dy)

Handles mouse motion and rotates the attached camera accordingly.

For more information about how to customize mouse movement, see the class documentation here WorldViewMouseRotatable().

2.20 peng3d.actor - Extendable Actor System

class peng3d.actor.Actor(peng, world, uuid=None, pos=[0, 0, 0])

Actor object, base class for all other Actors in the world.

An actor represents an object in the world, for example the player, an animal, enemy or dropped item.

Everything that is not part of the terrain should be an actor.

The default actor does not do anything, you should look at the subclasses for more information.

addController(controller)

Adds a controller to the actor.

A controller can control its actor and can act as a bridge between actor and user inputs.

Controllers may be added anytime during the lifetime of an actor.

on move (old)

Fake event handler called if the location of this actor changes.

This handler is called after the location has changed.

Parameters old (list) – The previous position

pos

Property allowing access to the position of this actor.

This actor is read-write but calls on_move() if it is set.

render (view=None)

Called by World.render3d() to render this actor.

By default, this method calls the draw method of its model, if any.

For custom render behavior, it is recommended to extend this method or modify the model.

setAnimation (animation, transition=None, force=False)

Sets the animation the model of this actor should show.

animation is the name of the animation to switch to.

transition can be used to override the transition between the animations.

force can be used to force reset the animation even if it is already running.

If there is no model set for this actor, a RuntimeError will be raised.

setModel (model)

Sets the model this actor should use when drawing.

This method also automatically initializes the new model and removes the old, if any.

class peng3d.actor.**RotatableActor** (peng, world, uuid=None, pos=[0, 0, 0], rot=[0, 0]) Actor that can also be rotated.

This subclass adds a rotational value to the actor and a method to move the actor along the current rotation.

move (dist)

Moves the actor using standard trigonometry along the current rotational vector.

Parameters dist (float) – Distance to move

Todo: Test this method, also with negative distances

on rotate (old)

Fake event handler called if the rotation of this actor changes.

This handler is called after the rotation has been made.

Parameters old (tuple) – Old rotation before rotating

rot

Property for accessing the rotation of this actor.

Rotation is a tuple of (x, y) where y is clamped to -90 and 90. x rolls over at 360, resulting in a seamless experience for players.

This property may also be written to, this calls on_rotate().

peng3d.actor.RotateableActor

alias of peng3d.actor.RotatableActor

class peng3d.actor.Controller(actor)

Base class for all controllers.

Controllers define behavior of Actors and can be used to control them via e.g. the keyboard or an AI.

Every controller is bound to its actor and can be enabled and disabled individually. You may also deactivate all controllers of an Actor by setting the enabled key of Actor.controlleroptions to False.

enabled

Property allowing to get and set if this controller should be active.

When getting this property, the result of ANDing the internal flag and the actor flag is returned.

When setting, only the local internal flag is set, allowing other controllers to still work.

Raises AssertionError – when the supplied value is not of type bool

registerEventHandlers()

Method to be overridden by subclasses for registering event handlers.

Automatically called upon object creation.

2.21 peng3d.actor.player - Player Actors

```
class peng3d.actor.player.BasicPlayer(peng, world, uuid=None, pos=[0, 0, 0], rot=[0, 0])
Basic Player class, subclass of RotatableActor().
```

This class adds no features currently, it can be used to identify player actors via isinstance().

```
class peng3d.actor.player.FirstPersonPlayer(peng, world, uuid=None, pos=[0, 0, 0], rot=[0, 0])
```

Old class allowing to create standard first-person players easily.

```
Deprecated See EgoMouseRotationalController() and FourDirectionalMoveController() instead
```

get motion vector()

Returns the movement vector according to held buttons and the rotation.

Returns 3-Tuple of (dx, dy, dz)

Return type tuple

update(dt)

Internal method used for moving the player.

Parameters dt (float) – Time delta since the last call to this method

class peng3d.actor.player.FourDirectionalMoveController(*args, **kwargs)

Controller allowing the user to control the actor with the keyboard.

You can configure the used keybinds with the *controls.controls.forward* etc. The keybinds can also be changed with their keybindname, e.g. peng3d:actor.<actor uuid>.player.controls.forward for forward.

The movement speed may also be changed via the movespeed instance attribute, which defaults to controls.controls.movespeed.

You may also access the currently held keys via move, which is a list with 2 items, forwards/backwards and left/right.

get_motion_vector()

Returns the movement vector according to held buttons and the rotation.

Returns 3-Tuple of (dx, dy, dz)

Return type tuple

registerEventHandlers()

Registers needed keybinds and schedules the update () Method.

You can control what keybinds are used via the controls.controls.forward etc. Configuration Values.

update(dt)

Should be called regularly to move the actor.

This method does nothing if the enabled property is set to false.

Note that this method is called automatically and should not be manually called.

class peng3d.actor.player.EgoMouseRotationalController(*args, **kwargs)

Controller allowing the user to rotate the actor with the mouse.

registerEventHandlers()

Registers the motion and drag handlers.

Note that because of the way pyglet treats mouse dragging, there is also an handler registered to the on_mouse_drag event.

class peng3d.actor.player.BasicFlightController(*args, **kwargs)

Controller allowing the user to move up and down with the jump and crouch controls.

The used keybinds may be configured via controls.controls.crouch and controls.controls.jump.

The vertical speed used when flying may be configured via controls.controls.verticalspeed or the speed attribute.

registerEventHandlers()

Registers the up and down handlers.

Also registers a scheduled function every 60th of a second, causing pyglet to redraw your window with 60fps.

update(dt)

Should be called regularly to move the actor.

This method does nothing if the enabled property is set to False.

This method is called automatically and should not be called manually.

2.22 peng3d.keybind - Dynamic Keybinding System

class peng3d.keybind.KeybindHandler(peng: peng3d.Peng)

Handler class that automatically converts incoming key events to key combo events.

A keybinding always is of format [MOD1-[MOD2-]] KEY with potentially more modifiers.

See MODNAME2MODIFIER for more information about existing modifiers.

Note that the order in which modifiers are listed also is the order of the above listing.

Keybindings are matched exactly, and optionally a second time without the modifiers listed in <code>OPTIONAL_MODNAMES</code> if <code>controls.keybinds.strict</code> is set to False.

add (keybind: str, kbname: str, handler: Callable[[int, int, bool], Any], mod: bool = True) \rightarrow None Adds a keybind to the internal registry.

Keybind names should be of the format namespace:category.subcategory.namee.g. peng3d:actor.player.controls.forward for the forward key combo for the player actor.

Parameters

- **keybind** (str) Keybind string, as described above
- **kbname** (str) Name of the keybind, may be used to later change the keybinding without re-registering
- handler (function) Function or any other callable called with the positional arguments (symbol, modifiers, release) if the keybind is pressed or released
- mod (int) If the keybind should respect modifiers

changeKeybind ($kbname: str, combo: str) \rightarrow None$

Changes a keybind of a specific keybindname.

Parameters

- **kbname** (str) Same as kbname of add ()
- combo (str) New key combination

handle_combo (combo: str, symbol: int, modifiers: int, release: bool = False, mod: bool = True) \rightarrow None

Handles a key combination and dispatches associated events.

First, all keybind handlers registered via <code>add()</code> will be handled, then the pyglet event <code>on_key_combo</code> with params (combo, symbol, modifiers, release, mod) is sent to the <code>Peng()</code> instance.

Also sends the events peng3d:keybind.combo, peng3d:keybind.combo.press and :peng3d:event'peng3d:keybind.combo.release'.

Params str combo Key combination pressed

Params int symbol Key pressed, passed from the same argument within pyglet

Params int modifiers Modifiers held while the key was pressed

Params bool release If the combo was released

Params bool mod If the combo was sent without mods

 $mod_is_held(modname: str, modifiers: int) \rightarrow bool$

Helper method to simplify checking if a modifier is held.

Parameters

- modname (str) Name of the modifier, see MODNAME2MODIFIER
- modifiers (int) Bitmask to check in, same as the modifiers argument of the on_key_press etc. handlers

peng3d.keybind.KeybindHandlerFunc = typing.Callable[[int, int, bool], typing.Any]
Custom type for a keybind handler function.

See KeybindHandler.add() for more details regarding the signature.

peng3d.keybind.MODNAME2MODIFIER

Ordered Bidict that maps between user-friendly names and internal constants.

Note that since this is a bidict, you can query the reverse mapping by accessing MODNAME2MODIFIER.inv. The non-inverse mapping maps from user-friendly name to internal constant.

This mapping is used by the Keybind system to convert the modifier constants to names.

The Mapping is as follows:

Name	Pyglet constant	Notes
ctrl	key.MOD_ACCEL	
alt	key.MOD_ALT	1
shift	key.MOD_SHIFT	
option	key.MOD_OPTION	
capslock	key.MOD_CAPSLOCK	
numlock	key.MOD_NUMLOCK	
scrollock	key.MOD_SCROLLOCK	

1: automatically replaced by MOD_CTRL on Darwin/OSX

peng3d.keybind.MOD_RELEASE = 32768

Fake modifier applied when a key is released instead of pressed.

This modifier internally has the value of 1<<15 and should thus be safe from any added modifiers in the future.

Note that this modifier is only applied within keybinds, not in regular on_key_down and on_key_up handlers.

peng3d.keybind.**OPTIONAL_MODNAMES** = ['capslock', 'numlock', 'scrollock'] List of modifiers that are not substantial to a key combo.

If the *controls.keybinds.strict* option is disabled, every key combo is emitted with and without the modifiers in this list. Else, only the combo with these modifiers is emitted.

This may cause no more combos to get through if numlock or capslock are activated.

2.23 peng3d.config - Configuration system

```
peng3d.config.CFG_FOG_DEFAULT = {'color': None, 'enable': False, 'end': 160, 'start':
    Default fog configuration.
```

This configuration simply disables fog.

```
peng3d.config.CFG_LIGHT_DEFAULT = {'enable': False}
```

Default lighting configuration.

This configuration simply disables lighting.

```
peng3d.config.DEFAULT_CONFIG
```

Default configuration values.

All default configuration values are stored here, for more information about specific config values, see *Configuration Options for peng3d*.

```
class peng3d.config.Config(config=None, defaults=None)
```

Configuration object imitating a dictionary.

config can be any dictionary-style object and is used to store the configuration set by the user. This object only needs to implement the __getitem__, __setitem__ and __contains__ special methods.

defaults can be any dictionary-style object and is only read from in case the config object does not contain the key. Every config object is stackable, e.g. you can pass another <code>Config</code> object as the defaults object.

Example for stacking configs:

```
>>> myconf = Config()
>>> myconf[ = Config(defaults=myconf)
>>> myconf["foo"] = "bar"
>>> print(myconf2["foo"])
bar
>>> myconf2["bar"] = "foo"
>>> print(myconf2["bar"])
foo
>>> print(myconf["bar"])
Traceback (most recent call last):
...
KeyError: Key "bar" does not exist
```

There is no limit in stacking configurations, though higher-stacked configs may get slow when defaulting due to propagating through the whole chain.

2.24 peng3d.util - Utility Functions and Classes

```
class peng3d.util.WatchingList(l, callback=None)
    Subclass of list() implementing a watched list.
```

A WatchingList will call the given callback with a reference to itself whenever it is modified. Internally, the callback is stored as a weak reference, meaning that the creator should keep a reference around.

This class is used in peng3d.gui.widgets.BasicWidget() to allow for modifying single coordinates of the pos and size properties.

```
peng3d.util.register_pyglet_handler(peng, func, event, raiseErrors=False)
```

Registers the given pyglet-style event handler for the given pyglet event.

This function allows pyglet-style event handlers to receive events bridged through the peng3d event system. Internally, this function creates a lambda function that decodes the arguments and then calls the pyglet-style event handler.

The raiseErrors flag is passed through to the peng3d event system and will cause any errors raised by this handler to be ignored.

See also:

See addEventListener() for more information.

class peng3d.util.ActionDispatcher

Helper Class to be used to enable action support.

Actions are simple callbacks that are specific to the instance they are registered with.

To be able to use actions, a class must be a subclass of ActionDispatcher().

Creation of required data structures is handled automatically when the first action is added.

Internally, this object uses the actions attribute to store a map of action names to a list of callbacks.

```
addAction (action: str, func: Callable, *args, **kwargs)
```

Adds a callback to the specified action.

All other positional and keyword arguments will be stored and passed to the function upon activation.

```
doAction (action: str)
```

Helper method that calls all callbacks registered for the given action.

Smart registry allowing easy management of mappings from int to str and vice versa.

Note that bidict is required to be able to use this class.

data may be a dictionary to initialize the registry with. Only dictionaries gotten from the data property should be used.

reuse_ids specifies whether or not the automatic ID generator should re-use old, now unused IDs. See genNewID() for more information.

start_id is the lowest ID that will be generated by the automatic ID generator.

max_id is the highest ID that will be generated by the automatic ID generator. Should this limit by reached, an AssertionError will be raised.

default_reg may be a dictionary mapping IDs to names. It will only be used if data did not already contain a registry.

It is possible to access the registry via the dict-style reg[key] notation. This will return the name of whatever object was used as the key.

Registering is also possible in a similar manner, like reg[name] = id. id may be None to automatically generate one.

This class also supports the in operator, note that both IDs and names are checked.

data

Read-only property to access the internal data.

This is a dictionary containing all information necessary to re-create the registry via the data argument.

The returned object is fully JSON/YAML/MessagePack serializable, as it only contains basic python data types.

```
genNewID() \rightarrow int
```

Generates a new ID.

If reuse_ids was false, the new ID will be read from an internal counter which is also automatically increased. This means that the newly generated ID is already reserved.

If reuse_ids was true, this method starts counting up from start_id until it finds an ID that is not currently known. Note that the ID is not reserved, this means that calling this method simultaneously from multiple threads may cause the same ID to be returned twice.

Additionally, if the ID is greater or equal to max_id, an AssertionError is raised.

```
normalizeID(in\_id: Union[int, str]) \rightarrow int
```

Takes in an object and normalizes it to its ID/integer representation.

Currently, only integers and strings may be passed in, else a TypeError will be thrown.

```
normalizeName (in\_name: Union[int, str]) \rightarrow str
```

Takes in an object and normalizes it to its name/string.

Currently, only integers and strings may be passed in, else a TypeError will be thrown.

```
\textbf{register} (\textit{name: str}, \textit{force\_id: Optional[int]} = \textit{None}) \ \rightarrow \text{int}
```

Registers a name to the registry.

name is the name of the object and must be a string.

force_id can be optionally set to override the automatic ID generation and force a specific ID.

Note that using force_id is discouraged, since it may cause problems when reuse_ids is false.

```
peng3d.util.default(arg: Optional[T], _default: T) \rightarrow T
```

Small helper function that replaces the given argument with a default if the argument is None.

This can also be written as a ternary expression in-line, but using this function makes the purpose clearer and easier to read.

Special property decorator/class that allows for easy defaulting of attributes to the parents' attributes.

This class can either be used as a decorator or as a class attribute.

For decorator usage, simply decorate an empty method with the name of the attribute to default, passing the name of the attribute the parent is stored in:

```
class A:
    @default_property("parent")
    def my_attr(self): ...
```

Accessing my_attr will then return the value of the my_attr attribute of the parent attribute of the class instance. Setting my_attr will not touch the attribute of the same name of the parent, but rather set an internal attribute, causing all subsequent accesses to return this local attribute.

Setting the property to None will reset the whole mechanism, causing all accesses until the next write to return the defaulted value.

Internally, all this is handled by a shadow attribute with the same name as the actual property, but prefixed by an underscore. This internal attribute may also be written to directly, which is especially useful in constructors.

Deleting the property will also just reset it, until it is next written.

Alternatively, this class can also be used as a class attribute, for the same effect as described above:

```
class A:
    my_attr = default_property("parent")
```

Note that this only works if the property is defined in the class body. Later assignment to the class object is possible, but requires providing the name argument, since auto-detecting the attribute name is then not possible.

To simplify creation, it is possible to set the PARENT_ATTR class attribute to provide a default first argument to <code>default_property</code>. This is usually worthwhile if multiple <code>default_properties</code> are used within the same class hierarchy, especially since the class attribute value can be inherited.

The parent_attr keyword-only argument may be passed to override what attribute of the parent is used as a default.

2.25 peng3d.util.gui - GUI Utility Functions and Classes

peng3d.util.gui.mouse_aabb (mpos: List[float], size: List[float], pos: List[float]) \rightarrow bool AABB Collision checker that can be used for most axis-aligned collisions.

Intended for use in widgets to check if the mouse is within the bounds of a particular widget.

```
peng3d.util.gui.points2htmlfontsize (points: float) \rightarrow float Approximate font size converter, converts from Points to HTML <font> tag font sizes.
```

Note that this method is very inaccurate, since there are only seven possible output values that represent at least 25 input values. When in doubt, this function always rounds down, e.g. every input value less than eight is converted to HTML size 1.

```
class peng3d.util.gui.ResourceGroup (data, parent=None)
    Pyglet Group that represents a Resource as returned by the ResourceManager().
```

This Group should automatically merge different groups with different resources that are on the same texture atlas.

2.26 peng3d.util.types - Custom Types

This module contains various helper types used throughout peng3d.

Most of these types are aliases, which ensure compatibility with existing applications that for example pass in literal values (which wouldn't be of a custom type without casting).

```
peng3d.util.types.ColorRGB = typing.List[int]
    RGB Color represented as three integers from zero to 255.

peng3d.util.types.ColorRGBA = typing.List[int]
    RGBA Color represented as four integers from zero to 255.

peng3d.util.types.ColorRGBFloat = typing.List[float]
    RGB Color represented as three floats from zero to one.

peng3d.util.types.ColorRGBAFloat = typing.List[float]
    RGBA Color represented as four floats from zero to one.

peng3d.util.types.BorderStyle = typing.Union[typing.Type[ForwardRef('Borderstyle')], str]
    Border style identifier.
```

Either a subclass of Borderstyle () or a string identifier.

See also:

See setBackground() for further details.

peng3d.util.types.DynPosition = typing.Union[typing.List[float], typing.Callable[[float, f. Dynamic position of a widget or container.

Can be either a static position as a list, a callback function or a LayoutCell.

peng3d.util.types.DynSize = typing.Union[typing.List[float], typing.Callable[[float, float] Dynamic size of a widget or container.

Can be either a static size as a list or a callback function. May be None if the position is a Layout Cell.

peng3d.util.types.DynTranslateable = typing.Union[str, ForwardRef('_LazyTranslator')]

A string that may be either fixed, translated or even dynamically translated.

If a method or class accepts this type, it means that it supports dynamic translation of this attribute, unless indicated otherwise in its documentation.

2.27 peng3d.version - Version information

peng3d.version.VERSION

Full version number, compliant with semantic versioning

Used to display the version in the title of the documentation.

Also used for the version in setup.py.

Changed in version 1.10.0: Before 1.10.0, peng3d did not quite comply with semantic versioning. This is mainly due to the a1 suffix on most version names.

peng3d.version.RELEASE

Currently the same as VERSION.

Used to display the version on the top-right of the documentation.

Events used by Peng3d

See also:

This document describes the events used by peng3d, see <code>peng3d.peng.Peng.sendEvent()</code> for information about the event system itself.

Note that there is no completely safe way to get a list of all events used by an application, but you should get most events by setting the config value debug.events.dumpfile to a valid file name and running the application in question. Make sure to trigger all events, or else they may not appear in the list.

This document is sectioned after the categories of events used.

Note that many applications will add their own events, which should be listed in their documentation.

3.1 Peng3d Events using sendEvent()

Events listed here can be sent via the <code>sendEvent()</code> method and be received via <code>addEventListener()</code>.

If possible, this system should be used, as it is better and has many improvements over previous systems.

Most of these events use a dictionary containing at least the peng key as their data parameter.

3.1.1 Special events

These events are special and should not be sent manually, they are mostly for backwards-compatibility.

peng3d:pyglet

Special event sent by <code>sendPygletEvent()</code> for compatibility.

Additional parameters:

args is a list of the given parameters.

window is the window this event originated from.

src is the object this event was sent via.

event_type is the pyglet event type.

See also:

See pyglet: * for another way of accessing pyglet events.

pyglet:*

Special event sent by <code>sendPygletEvent()</code> for compatibility.

See peng3d:pyglet for more information on the given parameters.

3.1.2 peng3d:peng. * Events Category

These events are typically sent by the main Peng () instance.

peng3d:peng.run

Triggered once when calling run () just before starting the event loop.

Additional parameters are window set to the main window object and evloop set to the argument of the same name.

peng3d:peng.exit

Triggered once the pyglet event loop exits.

Note that the calling method may cause the program to continue running.

This event has no additional parameters.

3.1.3 peng3d:window. * Events Category

These events are sent to mark changes to an instance of PengWindow().

Note that some of these events are not sent by the window itself and do not require a window to exist.

```
peng3d:window.create.pre
peng3d:window.create
peng3d:window.create.post
```

These events are sent when the main window is created.

The event peng3d:window.create.pre has the additional parameter cls containing the class used to create the window.

The events peng3d:window.create and peng3d:window.create.post both have the additional parameter window set to the window object.

Note that the window attribute of Peng () is only available after the handling of peng3d:window.create has finished.

peng3d:window.menu.add

Triggered whenever a menu is added to the window.

Additional parameters are window set to the window object and menu set to the menu object.

peng3d:window.menu.change

Triggered whenever the active menu is changed.

This event is sent after other event handlers have finished processing.

Additional parameters:

window is the current window object.

old is the name of the old menu. This may be ${\tt None}$ if there was no active menu.

menu is the name of the new menu.

peng3d:window.toggle_exclusive

Triggered whenever the mouse exclusivity is changed via toggle_exclusivity().

Additional parameters are window set to the window object and exclusive set to the current exclusivity state.

3.1.4 peng3d:rsrc.* Events Category

These events are sent by the ResourceManager () to signal that either the manager itself was modified or a resource was changed.

```
peng3d:rsrc.init.pre
peng3d:rsrc.init
peng3d:rsrc.init.post
```

These events are sent when the resource manager is first initialized.

The event peng3d:rsrc.init.pre has the additional parameter basepath containing the base path of the new resource manager.

The events peng3d:rsrc.init and peng3d:rsrc.init.post both have the additional parameter rsrcMgr set to the newly created resource manager.

Note that the resourceMgr attribute of Peng() is only available after the handling of peng3d:rsrc.init has finished.

peng3d:rsrc.category.add

Sent when a new resource category is added.

The additional parameter category is set to the name of the new category.

peng3d:rsrc.tex.load

Sent when a texture resource is first loaded.

Additional parameters are name and category set to their corresponding arguments given to <code>loadTex()</code>.

peng3d:rsrc.model.load

Sent when a model resource is first loaded.

Additional parameters are name set to the name of the model.

3.1.5 peng3d:i18n. * Events Category

See also:

See TranslationManager () for more information about the translation system.

peng3d.i18n.set_lang

Sent whenever the default language is set.

Note that this event is sent regardless of whether or not the language actually changed.

Additional parameters are i18n, set to the translation manager, and lang set to the new language.

3.1.6 peng3d:keybind.* Events Category

These events usually mark an event related to a specific key combination.

See also:

See KeybindHandler () for more information on the keybind system.

peng3d:keybind.add

Triggered when a keybind is added to the system.

Additional parameters are all arguments given to add ().

peng3d:keybind.change

Triggered when a keybind is changed.

Additional parameters are all arguments given to changeKeybind().

```
peng3d:keybind.combo
peng3d:keybind.combo.press
peng3d:keybind.combo.release
```

These events are triggered whenever a key combination is detected.

Note that this event will be sent regardless of whether or not there are any handlers registered for the keybind in question.

peng3d:keybind.combo is always sent, and depending on the release flag, either peng3d:keybind.combo.press or peng3d:keybind.combo.release is also sent.

Additional parameters are the same as the arguments given to handle_combo().

3.2 Pyglet Events using sendPygletEvent()

Events listed here can be sent via the <code>sendPygletEvent()</code> method and be received via <code>addPygletListener()</code>.

There are also several events sent by pyglet itself, see the Pyglet Docs for more information.

Todo: Add docs for custom pyglet events.

Configuration Options for peng3d

Almost all important settings can be configured per-window or globally via the Peng.cfg or Window.cfg attributes.

4.1 Graphic Settings/OpenGL Base State

For most of these graphical settings, it is important to actually use the exact type specified. For example, you should only pass floats and not integers if the specified type is float.

graphics.clearColor

A 4-tuple of RGBA colors used to clear the window before drawing.

Each Color part should be a float between 0 and 1.

By default, this option is set to (0., 0., 0., 1.).

Be sure to verify that each value is a float, not an integer.

graphics.wireframe

A Boolean value determining the polygon-fill-mode used by OpenGL.

True results in GL_LINE being used, while False will result in GL_FILL being used.

This option can be used to create a wireframe-like mode.

The default value for this option is False.

Note: This option is always turned off by PengWindow.set2d() but re-enabled by PengWindow.set3d() if necessary.

graphics.fieldofview

An float value passed to gluPerspective() as the first argument.

For more information about this config option, see the GL/GLU documentation.

By default, this option is set to 65.0.

```
graphics.nearclip
graphics.farclip
```

An float value specifying the near and far clipping plane, respectively.

These clipping planes determine at what point vertices are cut off to save GPU cycles.

By default, graphics.nearclip equals 0.1 and graphics.farclip equals 10000.

4.1.1 Fog settings

graphics.fogSettings

Config() object storing the fog-specific settings.

To access fog settings, use peng.cfg["graphics.fogSettings"]["<configoption>"] as appropriate.

graphics.fogSettings["enable"]

A boolean value activating or deactivating the OpenGL fog.

By default disabled.

graphics.fogSettings["color"]

A 4-Tuple representing an RGB Color.

Note that the values should be $0 \le n \le 1$, not in range (0,256).

For most cases, this value should be set to the clear color, else, visual artifacts may occur.

```
graphics.fogSettings["start"]
graphics.fogSettings["end"]
```

Defines start and end of the fog zone.

The end value should be nearer than the far clipping plane to avoid cut-off vertices.

Each value should be a float and is measured in standard OpenGL units.

By default, the fog starts at 128 units and ends 32 units further out.

4.1.2 Light settings

graphics.lightSettings

Config() object storing the light settings.

To access light settings, use peng.cfg["graphics.lightSettings"]["<configoption>"] as appropriate.

graphics.lightSettings["enable"]

A boolean value activating or deactivating the light config.

By default disabled.

Todo: Implement light settings with shader system

4.2 Controls

Note that most of these config values are read when the appropriate objects are initialized, this means that you should consult the objects documentation for how to change the option at runtime.

4.2.1 Mouse

controls.mouse.sensitivity

Degrees to move per pixel traveled by the mouse.

This applies to both horizontal and vertical movement.

Defaults to 0.15.

4.2.2 Keyboard

controls.controls.movespeed

Speed multiplier for most movements.

Defaults to 10.0.

controls.controls.verticalspeed

Speed multiplier for vertical movement.

Defaults to 5.0.

These keys are all registered with the mod flag set to False, thus they will ignore any modifiers.

```
controls.controls.forward
controls.controls.backward
controls.controls.strafeleft
controls.controls.straferight
```

Four basic movement keys.

Each of these keys can be changed individually.

Defaults are w, s, a and d, respectively.

controls.controls.jump

Jump key.

Defaults to space.

controls.controls.crouch

Crouch key.

Defaults to lshift.

4.2.3 Commonly used Key Combination Configuration Values

```
controls.keybinds.common.copy
controls.keybinds.common.paste
controls.keybinds.common.cut
```

Key Combinations used to be used by various parts of the GUI.

Currently used by the <code>peng3d.gui.text.TextInput()</code> Widget for basic clipboard operations.

By default, these are set to the commonly used values of Ctrl-C for Copy, Ctrl-V for Paste and Ctrl-X for Cutting.

4.2. Controls 79

4.2.4 General Controls Configuration Values

controls.keybinds.strict

Whether or not keybindings should be strict.

See peng3d.keybind.KeybindHandler() for more information.

4.3 Debug Options

All of these options are disabled by default.

controls.keybinds.debug

If enabled, all pressed keybinds will be printed.

debug.events.dump

If enabled, all events are printed including their arguments.

Note that on_draw and on_mouse_motion are never printed to avoid excessive outputs.

debug.events.logerr

If enabled, Exceptions catched during event handling are printed.

Note that only AttributeError exceptions are catched and printed, other exceptions will propagate further.

debug.events.register

If enabled, all event handler registrations are printed.

debug.events.dumpfile

If not an empty string, this should point to a valid file path for dumping all event names.

If enabled, all event handler registrations and event sends will be logged to this file. Note that only the name of the event without data is stored and automatically deduplicated.

Defaults to "".

4.4 Resource Options

rsrc.enable

Enables or Disables the resource module.

By default enabled.

rsrc.basepath

Base directory of the Resource Manager.

By default determined via pyglet.resource.get_script_home().

rsrc.maxtexsize

Maximum Texture size per bin.

Limits the texture in size, useful if the graphics card has big textures (16kx16k) but only few textures will be needed.

By default set to 1024.

4.5 Translation Options

i18n.enable

Enables or Disables the i18n module.

By default enabled.

i18n.lang

Determines the default language selected upon startup.

Note that setting this config option after creating the first window will have no effect. Use setLang() instead.

Currently defaults to en, but may be changed to operating system language in the future.

4.6 Event Options

events.removeonerror

If True, automatically removes erroring event handlers. Note that the raiseErrors parameter takes precedent over this setting.

Defaults to True.

events.maxignore

An integer number defining the maximum amount of ignored event messages to write to the log file.

This setting is per event, not globally.

Defaults to 3.

4.7 Other Options

pyglet.patch.patch_float2int

Enables the float2int patch for pyglet.

See peng3d.pyglet_patch.patch_float2int() for more information.

Enabled by default.

Todo: Implement more config options

CHAPTER 5

Indices and tables

- genindex
- modindex
- search

Python Module Index

р

```
peng3d, 11
peng3d.actor, 63
peng3d.actor.player,64
peng3d.camera,60
peng3d.config,68
peng3d.gui,18
peng3d.gui.button, 23
peng3d.qui.container,39
peng3d.gui.layered,33
peng3d.gui.layout,31
peng3d.gui.menus,27
peng3d.gui.slider,43
peng3d.gui.style,46
peng3d.gui.text,41
peng3d.gui.widgets, 20
peng3d.i18n,52
peng3d.keybind,66
peng3d.layer, 15
peng3d.menu, 17
peng3d.model, 54
peng3d.peng, 11
peng3d.resource, 51
peng3d.util,68
peng3d.util.gui,71
peng3d.util.types,71
peng3d.version,72
peng3d.window, 13
peng3d.world,61
```

86 Python Module Index

$\verb"addImage"()" (peng 3d.gui.layered. DynImageWidgetLayer")$
method), 35
addLayer() (peng3d.gui.layered.LayeredWidget method), 33
addLayer() (peng3d.menu.Menu method), 18
addMenu() (peng3d.window.PengWindow method), 13
method), 11 (peng3d.peng.Peng
addRegion() (peng3d.model.Bone method), 56
<pre>addStyle() (peng3d.gui.layered.BaseBorderWidgetLaye</pre>
addSubMenu() (peng3d.gui.GUIMenu method), 18 addView() (peng3d.world.World method), 61
maddWidget() (peng3d.gui.container.Container method), 39
addWidget() (peng3d.gui.SubMenu method), 19
addWorld() (peng3d.menu.BasicMenu method), 17
AdvancedProgressbar (class in peng3d.gui.slider),
43
AdvancedProgressSubMenu (class in peng3d.gui.menus), 31
Animation (class in peng3d.model), 58
ATTRIBUTES (peng3d.gui.style.Style attribute), 49 auto_exit (peng3d.gui.menus.ProgressSubMenu at-
tribute), 30
В
Background (class in peng3d.gui.widgets), 22
SubmergroundType (in module peng3d.util.types), 71
BaseBorderWidgetLayer (class in
ar peng3d.gui.layered), 37
BasicFlightController (class in
peng3d.actor.player), 65
BasicMenu (class in peng3d.menu), 17
BasicPlayer (class in peng3d.actor.player), 64 BasicWidget (class in peng3d.gui.widgets), 20
BasicWidgetLayer (class in peng3d.gui.layered), 33
Bone (class in peng3d.model), 55
border (peng3d.gui.layered.WidgetLayer attribute), 34 Borderstyle (class in peng3d.gui.style), 46

BorderStyle (in module peng3d.util.types), 71	debug.events.logerr,80
BORDERSTYLES (in module peng3d.gui.style), 48	debug.events.register,80
Button (class in peng3d.gui.button), 23	events.maxignore, 81
ButtonBackground (class in peng3d.gui.button), 24	events.removeonerror,81
ButtonBorderWidgetLayer (class in	graphics.clearColor,77
peng3d.gui.layered), 38	graphics.farclip,78
	graphics.fieldofview,77
C	graphics.fogSettings,78
	graphics.fogSettings["color"],78
± ```	graphics.fogSettings["enable"],78
peng3d.model), 54	graphics.fogSettings["end"],78
cam (peng3d.world.WorldView attribute), 62	graphics.fogSettings["start"],78
Camera (class in peng3d.camera), 60	graphics.lightSettings, 78
CameraActorFollower (class in peng3d.camera),	graphics.lightSettings["enable"],78
60	
cell_size (peng3d.gui.layout.GridLayout attribute),	graphics.nearclip,78
32	graphics.wireframe,77
CFG_FOG_DEFAULT (in module peng3d.config), 68	i18n.enable, 81
CFG_LIGHT_DEFAULT (in module peng3d.config), 68	i18n.lang,81
changeKeybind() (peng3d.keybind.KeybindHandler	<pre>pyglet.patch.patch_float2int,81</pre>
method), 66	rsrc.basepath, 80
changeMenu() (peng3d.window.PengWindow	rsrc.enable,80
method), 13	rsrc.maxtexsize, 80
changeSubMenu() (peng3d.gui.GUIMenu method),	ConfirmSubMenu (class in peng3d.gui.menus), 29
18	Container (class in peng3d.gui.container), 39
Checkbox (class in peng3d.gui.button), 27	ContainerButtonBackground (class in
CheckboxBackground (class in peng3d.gui.button),	peng3d.gui.container), 40
27	Controller (class in peng3d.actor), 64
cleanup() (peng3d.model.Model method), 59	controls.controls.backward
clickable (peng3d.gui.container.Container attribute),	configuration value, 79
39	controls.crouch
clickable (peng3d.gui.widgets.BasicWidget at-	configuration value, 79
tribute), 21	controls.forward
ColorRGB (in module peng3d.util.types), 71	configuration value,79
ColorRGBA (in module peng3d.util.types), 71	controls.jump
ColorRGBAFloat (in module peng3d.util.types), 71	configuration value,79
ColorRGBFloat (in module peng3d.util.types), 71	controls.movespeed
Config (class in peng3d.config), 68	configuration value,79
configuration value	controls.strafeleft
controls.controls.backward,79	configuration value,79
controls.controls.crouch, 79	controls.straferight
controls.controls.forward,79	configuration value, 79
controls.jump,79	controls.controls.verticalspeed
controls.controls.movespeed, 79	configuration value, 79
controls.controls.strafeleft,79	controls.keybinds.common.copy
controls.controls.straferight,79	configuration value, 79
controls.controls.verticalspeed, 79	controls.keybinds.common.cut
controls.keybinds.common.copy, 79	configuration value, 79
controls.keybinds.common.cut,79	controls.keybinds.common.paste
controls.keybinds.common.paste,79	configuration value, 79
controls.keybinds.debug, 80	controls.keybinds.debug
controls.keybinds.debug, 80 controls.keybinds.strict, 80	configuration value, 80
	controls.keybinds.strict
controls.mouse.sensitivity,79	configuration value, 80
debug.events.dump, 80	controls.mouse.sensitivity
debug.events.dumpfile,80	COLLETOID . WORDC . DCHDICIVICY

configuration value, 79 create() (peng3d.model.Model method), 59 createWindow() (peng3d.peng.Peng method), 12 CustomTextInputBackground (class in peng3d.gui.text), 42	draw() (peng3d.layer.LayerWorld method), 17 draw() (peng3d.menu.BasicMenu method), 17 draw() (peng3d.menu.Menu method), 18 draw() (peng3d.model.Model method), 59 DynImageWidgetLayer (class in peng3d.gui.layered), 35
D	DynPosition (in module peng3d.util.types), 72
data (peng3d.util.SmartRegistry attribute), 69	DynSize (in module peng3d.util.types), 72
debug.events.dump	DynTranslateable (in module peng3d.util.types), 72
configuration value, 80	
debug.events.dumpfile	E
configuration value, 80	EgoMouseRotationalController (class in
debug.events.logerr	peng3d.actor.player), 65
configuration value, 80	EmptyBackground (class in peng3d.gui.widgets), 23
debug.events.register	enabled (peng3d.actor.Controller attribute), 64
configuration value, 80	enabled (peng3d.gui.widgets.BasicWidget attribute),
default (peng3d.gui.text.TextInput attribute), 42	21
default() (in module peng3d.util), 70	ensureBones() (peng3d.model.Bone method), 56
DEFAULT_CONFIG (in module peng3d.config), 68	ensureModelData() (peng3d.model.Model method),
default_property (class in peng3d.util), 70	59
DEFAULT_STYLE (in module peng3d.gui.style), 50	events.maxignore
DEFER_BG (in module peng3d.gui.widgets), 22	configuration value,81
delete() (peng3d.gui.button.Button method), 24	events.removeonerror
delete() (peng3d.gui.layered.BasicWidgetLayer	configuration value, 81
method), 33	exitDialog() (peng3d.gui.menus.DialogSubMenu
delete() (peng3d.gui.layered.LayeredWidget	method), 29
<pre>method), 33 delete() (peng3d.gui.widgets.BasicWidget method),</pre>	F
21	FirstPersonPlayer (class in peng3d.actor.player),
deleteCategory()(peng3d.gui.menus.AdvancedProg	
method), 31	FlatBorder (class in peng3d.gui.style), 46
deleteCategory()(peng3d.gui.slider.AdvancedProgr	ressbarn_valid() (peng3d.gui.SubMenu method), 19
method), 44	FormattedLabelWidgetLayer (class in
delEventListener() (peng3d.peng.Peng method),	peng3d.gui.layered), 36
12	FourDirectionalMoveController (class in
delWidget() (peng3d.gui.SubMenu method), 19	peng3d.actor.player), 65
DialogSubMenu (class in peng3d.gui.menus), 28	FramedImageBackground (class in
discoverLangs() (peng3d.i18n.TranslationManager	peng3d.gui.button), 26
method), 52	FramedImageButton (class in peng3d.gui.button), 25
<pre>dispatch_event() (peng3d.window.PengWindow</pre>	FramedImageWidgetLayer (class in
doAction() (peng3d.util.ActionDispatcher method),	peng3d.gui.layered), 36
69	G
draw() (peng3d.gui.container.Container method), 39	
draw () (peng3d.gui.GUILayer method), 20	genNewID() (peng3d.util.SmartRegistry method), 69
draw () (peng3d.gui.GUIMenu method), 18	genVertices() (peng3d.gui.layered.BaseBorderWidgetLayer
draw() (peng3d.gui.layered.BasicWidgetLayer	method), 38
method), 33	genVertices() (peng3d.gui.layered.ButtonBorderWidgetLaye
draw() (peng3d.gui.layered.LayeredWidget method),	method), 39 get () (peng3d.gui.style.Style method), 49
33	get() (peng3a.gui.siyie.siyie method), get_cell() (peng3d.gui.layout.GridLayout method),
draw() (peng3d.gui.SubMenu method), 19	32
draw() (peng3d.gui.text.TextInput method), 42	get_colormap() (peng3d.gui.style.Borderstyle class
draw() (peng3d.gui.widgets.BasicWidget method), 21	
(, 4 - 9 - 9 - 9 - 9 - 9 - 9 - 9 - 9 - 9 -	method), 46

get_colormap() (peng3d.gui.style.FlatBorder class method), 46	<pre>getView() (peng3d.world.World method), 61 getWidget()</pre>
<pre>get_colormap() (peng3d.gui.style.GradientBorder</pre>	method), 39
	getWidget() (peng3d.gui.SubMenu method), 19 GradientBorder(class in peng3d.gui.style), 47
<pre>get_colormap() (peng3d.gui.style.MaterialBorder</pre>	graphics.clearColor
get_colormap() (peng3d.gui.style.OldshadowBorder	configuration value, 77
class method), 47	graphics.farclip
get_motion_vector()	configuration value, 78
(peng3d.actor.player.FirstPersonPlayer	graphics.fieldofview
method), 64	configuration value, 77
get_motion_vector()	graphics.fogSettings
(peng3d.actor.player.FourDirectionalMoveContro	
method), 65	graphics.fogSettings["color"]
getColors() (peng3d.gui.button.ButtonBackground	configuration value, 78
method), 24	graphics.fogSettings["enable"]
getColors() (peng3d.gui.container.ContainerButtonBa	
method), 40	graphics.fogSettings["end"]
getColors()(peng3d.gui.layered.BaseBorderWidgetLag	yer configuration value,78
method), 38	<pre>graphics.fogSettings["start"]</pre>
<pre>getGeometryType()</pre>	configuration value, 78
method), 57	graphics.lightSettings
getLayer() (peng3d.gui.layered.LayeredWidget	configuration value,78
method), 33	<pre>graphics.lightSettings["enable"]</pre>
getLength() (peng3d.model.Bone method), 56	configuration value,78
getLength() (peng3d.model.RootBone method), 57	graphics.nearclip
getMissingTexture()	configuration value,78
(peng3d.resource.ResourceManager method),	graphics.wireframe
51	configuration value,77
<pre>getModel() (peng3d.resource.ResourceManager</pre>	GridLayout (class in peng3d.gui.layout), 32
method), 51	grouper() (in module peng3d.model), 54
getModelData() (peng3d.resource.ResourceManager	GroupWidgetLayer (class in peng3d.gui.layered), 35
method), 51	GUILayer (class in peng3d.gui), 20
getPivotPoint() (peng3d.model.Bone method), 56	GUIMenu (class in peng3d.gui), 18
getPivotPoint() (peng3d.model.RootBone	H
method), 57	
<pre>getPos() (peng3d.gui.layered.WidgetLayer method),</pre>	handle_combo() (peng3d.keybind.KeybindHandler method), 66
method), 24	handleEvent () (peng3d.peng.Peng method), 12
getPosSize() (peng3d.gui.slider.SliderBackground	HeadlessPeng (class in peng3d.peng), 13
method), 45	HTMLLabelWidgetLayer (class in
getPosSize() (peng3d.gui.slider.VerticalSliderBackgromethod), 46	peng3d.gui.layered), 37 und I
getRot () (peng3d.model.Bone method), 56	1
getNet() (peng3d.gui.layered.WidgetLayer method),	i18n.enable
34	configuration value, 81
<pre>getState()</pre>	il8n.lang
method), 21	configuration value, 81
getTex() (peng3d.resource.ResourceManager	id (peng3d.model.Material attribute), 55
method), 51	ImageBackground (class in peng3d.gui.button), 25
getTexCoords() (peng3d.model.Region method), 58	ImageButton (class in peng3d.gui.button), 25
getTexInfo() (peng3d.model.Region method), 58	<pre>ImageButtonWidgetLayer (class in peng3d.gui.layered), 36</pre>
getVertices() (peng3d.model.Region method), 58	ImageWidgetLayer (class in peng3d.gui.layered), 35

init_bg() (peng3d.gui.button.ButtonBackground method), 24	label (peng3d.gui.layered.LabelWidgetLayer at- tribute), 36
init_bg() (peng3d.gui.button.CheckboxBackground method), 27	label (peng3d.gui.text.Label attribute), 41 label_cancel (peng3d.gui.menus.ConfirmSubMenu
init_bg()(<i>peng3d.gui.button.FramedImageBackground</i>	
method), 26	label_confirm(peng3d.gui.menus.ConfirmSubMenu
<pre>init_bg() (peng3d.gui.button.ImageBackground</pre>	attribute), 29
method), 25	label_main (peng3d.gui.menus.DialogSubMenu at-
<pre>init_bg() (peng3d.gui.slider.ProgressbarBackground</pre>	tribute), 29
method), 43	label_ok (peng3d.gui.menus.DialogSubMenu at-
<pre>init_bg() (peng3d.gui.slider.SliderBackground</pre>	tribute), 29 label_progressbar
init_bg()(peng3d.gui.text.CustomTextInputBackground	
method), 42	tribute), 30
	LabelWidgetLayer (class in peng3d.gui.layered), 36
method), 42	Layer (class in peng3d.layer), 15
<pre>init_bg() (peng3d.gui.widgets.Background method),</pre>	Layer2D (class in peng3d.layer), 16 Layer3D (class in peng3d.layer), 16
initialize()(<i>peng3d.gui.layered.BaseBorderWidgetL</i>	
method), 38	LayerGroup (class in peng3d.layer), 16
initialize()(<i>peng3d.gui.layered.DynImageWidgetLa</i>	
method), 35	Layout (class in peng3d.gui.layout), 31
initialize()	etLayeoutCell (class in peng3d.gui.layout), 32
method), 36	<pre>loadDomain() (peng3d.i18n.TranslationManager</pre>
initialize() (peng3d.gui.layered.ImageWidgetLayer	method), 52
method), 35	loadModel() (peng3d.resource.ResourceManager
initialize() (peng3d.gui.layered.WidgetLayer	method), 51
method), 34	loadModelData() (peng3d.resource.ResourceManage
IS_CLICKABLE (peng3d.gui.widgets.BasicWidget attribute), 21	method), 51 loadTex() (peng3d.resource.ResourceManager
is_hovering (peng3d.gui.button.ButtonBackground	method), 52
attribute), 24	
is_hovering(peng3d.gui.layered.BaseBorderWidgetLa attribute), 38	yM Material (class in peng3d.model),55
is_hovering (peng3d.gui.widgets.Background at-	MaterialBorder (class in peng3d.gui.style), 48
tribute), 22	Menu (class in peng3d.menu), 18
is_overridden() (peng3d.gui.style.Style method),	menu (peng3d.window.PengWindow attribute), 14
49	<pre>mod_is_held() (peng3d.keybind.KeybindHandler</pre>
I	method), 67
U	MOD_RELEASE (in module peng3d.keybind), 67
JSONModelGroup (class in peng3d.model), 58	Model (class in peng3d.model), 59
JSONRegionGroup (class in peng3d.model), 58	MODNAME2MODIFIER (in module peng3d.keybind), 67
K	mouse_aabb() (in module peng3d.util.gui), 71 move() (peng3d.actor.RotatableActor method), 63
KeybindHandler (<i>class in peng3d.keybind</i>), 66	move () (pengsulacion. RolalableActor method), 03
KeybindHandlerFunc (in module peng3d.keybind),	N
67	n (peng3d.gui.slider.AdvancedProgressbar attribute), 44
•	n (peng3d.gui.slider.Progressbar attribute), 43
L	nmax (peng3d.gui.slider.AdvancedProgressbar at-
Label (class in peng3d.gui.text), 41	tribute), 44
label (peng3d.gui.button.Button attribute), 24	nmax (peng3d.gui.slider.Progressbar attribute), 43
label (peng3d.gui.layered.FormattedLabelWidgetLayer	nmin (peng3d.gui.slider.AdvancedProgressbar at-
attribute), 37	tribute), 44
	nmin (peng3d.gui.slider.Progressbar attribute), 43

```
norm_borderstyle() (in module peng3d.gui.style), on_redraw() (peng3d.gui.layered.DynImageWidgetLayer
                                                          method), 35
                                                  on redraw() (peng3d.gui.layered.FormattedLabelWidgetLayer
normalizeID() (peng3d.util.SmartRegistry method),
                                                          method), 37
normalizeName()
                         (peng3d.util.SmartRegistry
                                                  on_redraw() (peng3d.gui.layered.FramedImageWidgetLayer
        method), 70
                                                          method), 36
                                                  on_redraw() (peng3d.gui.layered.ImageWidgetLayer
O
                                                          method), 35
                                                  on_redraw() (peng3d.gui.layered.LabelWidgetLayer
offset (peng3d.gui.layered.WidgetLayer attribute), 34
                                                          method), 36
OldshadowBorder (class in peng3d.gui.style), 47
                                                  on_redraw()
                                                                    (peng3d.gui.layered.LayeredWidget
on_activate() (peng3d.camera.Camera method), 60
                                                          method), 33
on_draw() (peng3d.window.PengWindow method), 14
                                                  on_redraw()
                                                                      (peng3d.gui.layered.WidgetLayer
on_enter()
                    (peng3d.gui.container.Container
        method), 39
                                                          method), 34
                                                  on_redraw() (peng3d.gui.text.Label method), 41
on_enter() (peng3d.gui.GUIMenu method), 18
                                                  on_redraw() (peng3d.gui.text.TextInput method), 42
on_enter() (peng3d.menu.BasicMenu method), 17
                                                                      (peng3d.gui.widgets.BasicWidget
                                                  on_redraw()
on_enter() (peng3d.menu.Menu method), 18
                                                          method), 21
on_exit() (peng3d.gui.container.Container method),
                                                  on_redraw() (peng3d.gui.widgets.Widget method), 23
                                                  on redraw() (peng3d.layer.Layer method), 15
on_exit() (peng3d.menu.BasicMenu method), 17
                                                  on_rotate() (peng3d.actor.RotatableActor method),
on_exit() (peng3d.menu.Menu method), 18
on_key_press() (peng3d.world.WorldViewMouseRotatable
                                                  on_rotate() (peng3d.camera.Camera method), 60
        method), 62
                                                  OPTIONAL MODNAMES (in module peng3d.keybind), 67
on_menu_enter() (peng3d.layer.Layer method), 15
                          (peng3d.layer.LayerWorld
                                                  override_if_not_none() (peng3d.gui.style.Style
on_menu_enter()
                                                          method), 50
        method), 17
on_menu_enter()
                          (peng3d.world.WorldView
                                                  Р
        method), 62
on_menu_enter() (peng3d.world.WorldViewMouseRotatalpleng3d.gui.slider.Slider attribute), 45
                                                  parent (peng3d.gui.style.Style attribute), 50
        method), 62
                                                  password (peng3d.gui.text.PasswordInput attribute),
on_menu_exit() (peng3d.layer.Layer method), 15
on_menu_exit() (peng3d.layer.LayerWorld method),
                                                  PasswordInput (class in peng3d.gui.text), 42
        17
on_menu_exit() (peng3d.world.WorldView method),
                                                  Peng (class in peng3d.peng), 11
                                                  peng (peng3d.gui.widgets.Background attribute), 22
on_menu_exit() (peng3d.world.WorldViewMouseRotatqbdeng3d (module), 11
                                                  peng3d Event
        method), 62
on_mouse_drag() (peng3d.world.WorldViewMouseRotatablepeng3d.i18n.set_lang,75
        method), 62
                                                      peng3d:keybind.add,76
                                                      peng3d:keybind.change, 76
on_mouse_motion()
        (peng3d.world.WorldViewMouseRotatable
                                                      peng3d:keybind.combo,76
                                                      peng3d:keybind.combo.press,76
        method), 62
on_move() (peng3d.actor.Actor method), 63
                                                      peng3d:keybind.combo.release, 76
                                                      peng3d:peng.exit,74
on_move() (peng3d.camera.Camera method), 60
on_redraw() (peng3d.gui.button.Button method), 24
                                                      peng3d:peng.run,74
                                                      peng3d:pyglet,73
                    (peng3d.gui.container.Container
on_redraw()
        method), 39
                                                      peng3d:rsrc.category.add,75
                                                      peng3d:rsrc.init,75
on_redraw() (peng3d.gui.container.ScrollableContainer
                                                      peng3d:rsrc.init.post,75
        method), 40
on_redraw() (peng3d.gui.layered.BaseBorderWidgetLayer
                                                      peng3d:rsrc.init.pre,75
                                                      peng3d:rsrc.model.load,75
        method), 38
on_redraw() (peng3d.gui.layered.BasicWidgetLayer
                                                      peng3d:rsrc.tex.load,75
        method), 34
                                                      peng3d:window.create,74
                                                      peng3d:window.create.post,74
```

<pre>peng3d:window.create.pre,74 peng3d:window.menu.add,74</pre>	<pre>peng3d:rsrc.init.post peng3d Event,75</pre>
peng3d:window.menu.change,74	peng3d:rsrc.init.pre
peng3d:window.toggle_exclusive, 75	peng3d Event, 75
pyglet:*,74	peng3d:rsrc.model.load
peng3d.actor (module), 63	peng3d Event, 75
peng3d.actor.player(<i>module</i>), 64	peng3d:rsrc.tex.load
peng3d.accor.prayer (<i>module</i>), 64 peng3d.camera (<i>module</i>), 60	peng3d Event,75
peng3d.config (<i>module</i>), 68	peng3d:window.create
	peng3d Event, 74
peng3d.gui (<i>module</i>), 18 peng3d.gui.button (<i>module</i>), 23	peng3d Event, 74 peng3d:window.create.post
peng3d.gui.container (module), 39	peng3d Event,74
peng3d.gui.layered (module), 33	peng3d:window.create.pre
peng3d.gui.layout (module),31	peng3d Event,74
peng3d.gui.menus (module), 27	peng3d:window.menu.add
peng3d.gui.slider(module),43	peng3d Event,74
peng3d.gui.style(module),46	peng3d:window.menu.change
peng3d.gui.text (module),41	peng3d Event,74
peng3d.gui.widgets(module),20	peng3d:window.toggle_exclusive
peng3d.i18n (<i>module</i>), 52	peng3d Event,75
peng3d.i18n.set_lang	PengWindow (class in peng3d.window), 13
peng3d Event,75	points2htmlfontsize() (in module
peng3d.keybind(<i>module</i>),66	peng3d.util.gui), 71
peng3d.layer(<i>module</i>), 15	pos (peng3d.actor.Actor attribute), 63
peng3d.menu (<i>module</i>), 17	pos (peng3d.camera.Camera attribute), 60
peng3d.model (<i>module</i>), 54	pos (peng3d.camera.CameraActorFollower attribute)
peng3d.peng (module), 11	60
peng3d.resource (module), 51	pos (peng3d.gui.layout.LayoutCell attribute), 32
peng3d.util (module), 68	pos (peng3d.gui.widgets.BasicWidget attribute), 21
peng3d.util.gui (<i>module</i>),71	pos (peng3d.world.WorldView attribute), 62
peng3d.util.types (<i>module</i>), 71	<pre>postdraw() (peng3d.gui.layered.BasicWidgetLayer</pre>
peng3d.version(<i>module</i>),72	method), 34
peng3d.window(<i>module</i>), 13	<pre>postdraw() (peng3d.gui.layered.GroupWidgetLayer</pre>
peng3d.world(<i>module</i>),61	method), 35
peng3d:keybind.add	postdraw() (peng3d.layer.Layer method), 15
peng3d Event, 76	postdraw() (peng3d.layer.LayerGroup method), 16
peng3d:keybind.change	<pre>predraw() (peng3d.gui.layered.BasicWidgetLayer</pre>
peng3d Event, 76	method), 34
peng3d:keybind.combo	predraw() (peng3d.gui.layered.GroupWidgetLayer
peng3d Event, 76	method), 35
peng3d:keybind.combo.press	predraw() (peng3d.layer.Layer method), 16
peng3d Event, 76	predraw() (peng3d.layer.Layer2D method), 16
peng3d:keybind.combo.release	predraw() (peng3d.layer.Layer3D method), 16
peng3d Event, 76	predraw() (peng3d.layer.LayerGroup method), 16
peng3d:peng.exit	predraw() (peng3d.layer.LayerWorld method), 17
peng3d Event, 74	pressed (peng3d.gui.button.ButtonBackground at-
peng3d:peng.run	tribute), 25
peng3d Event, 74	pressed (peng3d.gui.button.ImageBackground at-
peng3d:pyglet	tribute), 25
peng3d Event,73	pressed (peng3d.gui.layered.BaseBorderWidgetLayer
peng3d:rsrc.category.add	attribute), 38
pengsd:rsrc.category.add peng3d Event,75	
peng3d:rsrc.init	pressed (peng3d.gui.text.TextInputBackground at- tribute), 42
peng3d Event, 75	pressed (peng3d.gui.widgets.Background attribute), 22

progress_n (peng3d.gui.menus.ProgressSubMenu attribute), 30	reg_vlist() (peng3d.gui.widgets.Background method), 22
progress_nmax(peng3d.gui.menus.ProgressSubMenu	Region (class in peng3d.model), 57
attribute), 30	register() (peng3d.util.SmartRegistry method), 70
progress_nmin (peng3d.gui.menus.ProgressSubMenu attribute), 31	register_pyglet_handler() (in module peng3d.util), 68
Progressbar (class in peng3d.gui.slider), 43	registerEventHandler() (peng3d.peng.Peng
ProgressbarBackground (class in	method), 12
peng3d.gui.slider), 43	registerEventHandlers()
ProgressSubMenu (class in peng3d.gui.menus), 30	(peng3d.actor.Controller method), 64
pyglet.patch.patch_float2int	registerEventHandlers()
configuration value, 81	(peng3d.actor.player.BasicFlightController
pyglet:*	method), 65
peng3d Event, 74	registerEventHandlers()
n	(peng3d.actor.player.EgoMouseRotationalControlle
R	method), 65
redraw() (peng3d.gui.container.Container method),	registerEventHandlers()
4()	(peng3d.actor.player.FourDirectionalMoveControlle
redraw() (peng3d.gui.widgets.BasicWidget method),	method), 65
21	registerEventHandlers()
redraw() (peng3d.layer.Layer method), 16	(peng3d.gui.widgets.BasicWidget method),
redraw() (peng3d.model.Model method), 60	22
redraw_bg() (peng3d.gui.button.ButtonBackground	regVList() (peng3d.gui.layered.BasicWidgetLayer
method), 25	method), 34
redraw_bg() (peng3d.gui.button.CheckboxBackground	RELEASE (in module peng3d.version), 72
method), 27	remove() (peng3d.model.Model method), 60
redraw_bg() (peng3d.gui.button.FramedImageBackgro	
method), 26	render3d() (peng3d.world.StaticWorld method), 62
	render3d() (peng3d.world.World method), 61
	resourceExists() (peng3d.resource.ResourceManager
method), 25	
redraw_bg() (peng3d.gui.slider.ProgressbarBackground	
method), 43	ResourceGroup (class in peng3d.util.gui), 71
	ResourceManager (class in peng3d.resource), 51
method), 45	resourceNameToPath()
redraw_bg()	und (peng3d.resource.ResourceManager method),
method), 42	52
redraw_bg() (peng3d.gui.text.TextInputBackground	RootBone (class in peng3d.model), 57
method), 42	rot (peng3d.actor.RotatableActor attribute), 64
redraw_bg() (peng3d.gui.widgets.Background	rot (peng3d.camera.Camera attribute), 60
method), 22	rot (peng3d.camera.CameraActorFollower attribute),
redraw_label() (peng3d.gui.button.Button method),	61
24	rot (peng3d.world.WorldView attribute), 62
	RotatableActor (class in peng3d.actor), 63
redraw_label() (peng3d.gui.button.Checkbox	
method), 27	RotateableActor (in module peng3d.actor), 64
redraw_label() (peng3d.gui.layered.FormattedLabelV	
method), 37	configuration value, 80
redraw_label()(<i>peng3d.gui.layered.LabelWidgetLaye</i>	
method), 36	configuration value, 80
redraw_label() (peng3d.gui.text.Label method), 41	rsrc.maxtexsize
redraw_label() (peng3d.gui.text.TextInput method),	configuration value, 80
42	run () (peng3d.peng.Peng method), 12
redraw_layer() (peng3d.gui.layered.LayeredWidget	run () (peng3d.window.PengWindow method), 14
method), 33	(,

S	<pre>switchImage() (peng3d.gui.layered.DynImageWidgetLayer</pre>
ScrollableContainer (class in	method), 35
peng3d.gui.container), 40	Т
send_form() (peng3d.gui.SubMenu method), 19	
sendEvent() (peng3d.peng.Peng method), 13	t () (peng3d.i18n.TranslationManager method), 53
sendPygletEvent() (peng3d.peng.Peng method),	target (peng3d.model.Material attribute), 55
13	tex_coords (peng3d.model.Material attribute), 55
set2d() (peng3d.window.PengWindow method), 14	texdata (peng3d.model.Material attribute), 55
set3d() (peng3d.window.PengWindow method), 14	text (peng3d.gui.text.PasswordInput attribute), 43
set_fps() (peng3d.window.PengWindow method), 14	text (peng3d.gui.text.TextInput attribute), 42
set_state() (peng3d.model.JSONModelGroup	TextInput (class in peng3d.gui.text), 41 TextInputBackground (class in peng3d.gui.text),
method), 58	12
set_state() (peng3d.model.JSONRegionGroup	TextSubMenu (class in peng3d.gui.menus), 30
method), 59	tickEntity() (peng3d.model.Animation method), 58
setActiveCamera() (peng3d.world.WorldView method), 62	t1() (peng3d.i18n.TranslationManager method), 53
setAnimation() (peng3d.actor.Actor method), 63	toggle_exclusivity()
setAnimation() (peng3d.model.Model method), 60	(peng3d.window.PengWindow method), 15
setBackground() (peng3d.gui.container.Container	ToggleButton (class in peng3d.gui.button), 26
method), 40	transformTexCoords() (peng3d.model.Material
setBackground() (peng3d.gui.SubMenu method), 19	method), 55
setBackground() (peng3d.gui.widgets.Widget	transformVertices() (peng3d.model.Bone
method), 23	method), 56
setBones() (peng3d.model.Animation method), 58	translate() (peng3d.i18n.TranslationManager
setLang() (peng3d.i18n.TranslationManager	method), 53
method), 53	translate_lazy() (peng3d.i18n.TranslationManager
setLength() (peng3d.model.Bone method), 56	method), 54
setModel() (peng3d.actor.Actor method), 63	TranslationManager (class in peng3d.i18n), 52
setParent() (peng3d.model.Bone method), 56	U
setRot() (peng3d.model.Bone method), 56	_
setRotate() (peng3d.model.Bone method), 56	unset_state() (peng3d.model.JSONModelGroup
setRotate() (peng3d.model.RootBone method), 57	method), 58
setup() (peng3d.window.PengWindow method), 15	unset_state() (peng3d.model.JSONRegionGroup
setupFog() (peng3d.window.PengWindow method), 15	method), 59
	unsetRotate() (peng3d.model.Bone method), 56 unsetRotate() (peng3d.model.RootBone method),
setupLight() (peng3d.window.PengWindow method), 15	57
setView() (peng3d.layer.LayerWorld method), 17	update() (peng3d.actor.player.BasicFlightController
size (peng3d.gui.layout.LayoutCell attribute), 32	method), 66
size (peng3d.gui.widgets.BasicWidget attribute), 22	update() (peng3d.actor.player.FirstPersonPlayer
Slider (class in peng3d.gui.slider), 44	method), 65
SliderBackground (class in peng3d.gui.slider), 45	update() (peng3d.actor.player.FourDirectionalMoveController
SmartRegistry (class in peng3d.util), 69	method), 65
startAnimation() (peng3d.model.Animation	update() (peng3d.gui.style.Style method), 50
method), 58	<pre>update_progressbar()</pre>
StaticWorld (class in peng3d.world), 61	(peng3d.gui.menus.ProgressSubMenu method),
stretchColors()(peng3d.gui.layered.BaseBorderWid	dgetLayer 31
method), 38	$\verb"updateCategory" () \textit{ (peng3d.gui.menus.} Advanced Progress SubMenu$
stretchColors() (peng3d.gui.layered.ButtonBorderW	·
method), 39	updateCategory() (peng3d.gui.slider.AdvancedProgressbar
Style (class in peng3d.gui.style), 48	method), 44
SubMenu (class in peng3d.gui), 19	V
submenu (peng3d.gui.GUIMenu attribute), 18	-
submenu (neng3d qui widgets Rackground attribute) 22	wagnitude () (in module neng3d model) 55

```
v_normalize() (in module peng3d.model), 55
value (peng3d.gui.slider.Progressbar attribute), 43
VERSION (in module peng3d.version), 72
VerticalSlider (class in peng3d.gui.slider), 45
VerticalSliderBackground (class in peng3d.gui.slider), 45
visible (peng3d.gui.slider), 45
visible (peng3d.gui.widgets.BasicWidget attribute), 22
```

W

WatchingList (class in peng3d.util), 68
Widget (class in peng3d.gui.widgets), 23
WidgetLayer (class in peng3d.gui.layered), 34
window (peng3d.gui.widgets.Background attribute), 22
World (class in peng3d.world), 61
WorldView (class in peng3d.world), 62
WorldViewMouseRotatable (class in peng3d.world), 62